



**MGC3140/MXG3141 GestIC<sup>®</sup>**  
**Library Interface Description**  
**User's Guide**

---

**Note the following details of the code protection feature on Microchip devices:**

- Microchip products meet the specifications contained in their particular Microchip Data Sheet.
- Microchip believes that its family of products is secure when used in the intended manner and under normal conditions.
- There are dishonest and possibly illegal methods being used in attempts to breach the code protection features of the Microchip devices. We believe that these methods require using the Microchip products in a manner outside the operating specifications contained in Microchip's Data Sheets. Attempts to breach these code protection features, most likely, cannot be accomplished without violating Microchip's intellectual property rights.
- Microchip is willing to work with any customer who is concerned about the integrity of its code.
- Neither Microchip nor any other semiconductor manufacturer can guarantee the security of its code. Code protection does not mean that we are guaranteeing the product is "unbreakable." Code protection is constantly evolving. We at Microchip are committed to continuously improving the code protection features of our products. Attempts to break Microchip's code protection feature may be a violation of the Digital Millennium Copyright Act. If such acts allow unauthorized access to your software or other copyrighted work, you may have a right to sue for relief under that Act.

---

Information contained in this publication is provided for the sole purpose of designing with and using Microchip products. Information regarding device applications and the like is provided only for your convenience and may be superseded by updates. It is your responsibility to ensure that your application meets with your specifications.

THIS INFORMATION IS PROVIDED BY MICROCHIP "AS IS". MICROCHIP MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND WHETHER EXPRESS OR IMPLIED, WRITTEN OR ORAL, STATUTORY OR OTHERWISE, RELATED TO THE INFORMATION INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE OR WARRANTIES RELATED TO ITS CONDITION, QUALITY, OR PERFORMANCE.

IN NO EVENT WILL MICROCHIP BE LIABLE FOR ANY INDIRECT, SPECIAL, PUNITIVE, INCIDENTAL OR CONSEQUENTIAL LOSS, DAMAGE, COST OR EXPENSE OF ANY KIND WHATSOEVER RELATED TO THE INFORMATION OR ITS USE, HOWEVER CAUSED, EVEN IF MICROCHIP HAS BEEN ADVISED OF THE POSSIBILITY OR THE DAMAGES ARE FORESEEABLE. TO THE FULLEST EXTENT ALLOWED BY LAW, MICROCHIP'S TOTAL LIABILITY ON ALL CLAIMS IN ANY WAY RELATED TO THE INFORMATION OR ITS USE WILL NOT EXCEED THE AMOUNT OF FEES, IF ANY, THAT YOU HAVE PAID DIRECTLY TO MICROCHIP FOR THE INFORMATION. Use of Microchip devices in life support and/or safety applications is entirely at the buyer's risk, and the buyer agrees to defend, indemnify and hold harmless Microchip from any and all damages, claims, suits, or expenses resulting from such use. No licenses are conveyed, implicitly or otherwise, under any Microchip intellectual property rights unless otherwise stated.

**Trademarks**

The Microchip name and logo, the Microchip logo, Adaptec, AnyRate, AVR, AVR logo, AVR Freaks, BesTime, BitCloud, chipKIT, chipKIT logo, CryptoMemory, CryptoRF, dsPIC, FlashFlex, flexPWR, HELDO, IGLOO, JukeBlox, KeeLoq, Kleer, LANCheck, LinkMD, maxStylus, maxTouch, MediaLB, megaAVR, Microsemi, Microsemi logo, MOST, MOST logo, MPLAB, OptoLyzer, PackTime, PIC, picoPower, PICSTART, PIC32 logo, PolarFire, Prochip Designer, QTouch, SAM-BA, SenGenuity, SpyNIC, SST, SST Logo, SuperFlash, Symmetricom, SyncServer, Tachyon, TimeSource, tinyAVR, UNI/O, Vectron, and XMEGA are registered trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

AgileSwitch, APT, ClockWorks, The Embedded Control Solutions Company, EtherSynch, FlashTec, Hyper Speed Control, HyperLight Load, IntelliMOS, Libero, motorBench, mTouch, Powermite 3, Precision Edge, ProASIC, ProASIC Plus, ProASIC Plus logo, Quiet-Wire, SmartFusion, SyncWorld, Temux, TimeCesium, TimeHub, TimePictra, TimeProvider, WinPath, and ZL are registered trademarks of Microchip Technology Incorporated in the U.S.A.

Adjacent Key Suppression, AKS, Analog-for-the-Digital Age, Any Capacitor, AnyIn, AnyOut, Augmented Switching, BlueSky, BodyCom, CodeGuard, CryptoAuthentication, CryptoAutomotive, CryptoCompanion, CryptoController, dsPICDEM, dsPICDEM.net, Dynamic Average Matching, DAM, ECAN, Espresso T1S, EtherGREEN, IdealBridge, In-Circuit Serial Programming, ICSP, INICnet, Intelligent Paralleling, Inter-Chip Connectivity, JitterBlocker, maxCrypto, maxView, memBrain, Mindi, MiWi, MPASM, MPF, MPLAB Certified logo, MPLIB, MPLINK, MultiTRAK, NetDetach, Omniscient Code Generation, PICDEM, PICDEM.net, PICKit, PICtail, PowerSmart, PureSilicon, QMatrix, REAL ICE, Ripple Blocker, RTAX, RTG4, SAM-ICE, Serial Quad I/O, simpleMAP, SimpliPHY, SmartBuffer, SMART-I.S., storClad, SQL, SuperSwitcher, SuperSwitcher II, Switchtec, SynchroPHY, Total Endurance, TSHARC, USBCheck, VariSense, VectorBlox, VeriPHY, ViewSpan, WiperLock, XpressConnect, and ZENA are trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

SQTP is a service mark of Microchip Technology Incorporated in the U.S.A.

The Adaptec logo, Frequency on Demand, Silicon Storage Technology, and Symmcom are registered trademarks of Microchip Technology Inc. in other countries.

GestIC is a registered trademark of Microchip Technology Germany II GmbH & Co. KG, a subsidiary of Microchip Technology Inc., in other countries.

All other trademarks mentioned herein are property of their respective companies.

© 2018-2021, Microchip Technology Incorporated, All Rights Reserved.

ISBN: 978-1-5224-7820-1

For information regarding Microchip's Quality Management Systems, please visit [www.microchip.com/quality](http://www.microchip.com/quality).

## Table of Contents

.....	<b>Preface 5</b>
<b>Chapter 1. Introduction</b>	
1.1 Purpose of this Document .....	10
1.2 GestIC® Software Architecture .....	10
1.3 GestIC® Library .....	11
1.4 Device Specific Limitations .....	11
<b>Chapter 2. GestIC® Host Interface</b>	
2.1 GestIC® Hardware Interface .....	12
<b>Chapter 3. GestIC® Library Message Interface</b>	
3.1 Messages Overview .....	13
3.2 Message Format .....	13
3.3 Message Header .....	14
3.4 Message Payload .....	14
3.5 Message Coding and Decoding .....	15
3.5.1 Header Extraction .....	15
3.5.2 Payload Extraction .....	16
3.6 Message Control Flow and Coding Examples .....	17
3.6.1 Message Control Flow .....	17
3.6.2 Read GestIC® Library Version .....	18
3.6.2.1 Example: Request_FW_Version Info .....	18
3.6.3 Run-Time Control .....	19
3.6.3.1 Example: Enable Approach Detection .....	19
3.6.3.2 Example: Enable All Gestures .....	19
3.6.3.3 Example: Enable Data Output .....	20
3.6.3.4 Example: Lock Data Output .....	20
3.6.4 Sensor Data Output .....	21
3.6.4.1 Example: Read Sensor Data Output .....	21
<b>Chapter 4. GestIC® Library Message Reference</b>	
4.1 Echo_Request .....	23
4.2 System_Status .....	23
4.3 Request_Message .....	27
4.4 Fw_Version_Info .....	28
4.5 Set_Runtime_Parameter .....	31
4.5.1 Trigger .....	32
4.5.2 Make Persistent .....	32
4.5.3 Analog Front-End (AFE) Category .....	33
4.5.3.1 Electrode Mapping .....	33
4.5.4 Digital Signal Processing (DSP) Category .....	34
4.5.4.1 Transmit Frequency Selection .....	34

---

---

4.5.4.2 Touch Detection .....	34
4.5.4.3 Approach Detection .....	34
4.5.5 System Category .....	35
4.5.5.1 AirWheel .....	35
4.5.5.2 Gesture Processing (HMM) .....	35
4.5.5.3 Calibration Operation Mode .....	36
4.5.5.4 Data Output Enable Mask .....	37
4.5.5.5 Data Output Lock Mask .....	38
4.5.5.6 Data Output Request Mask .....	39
4.6 Sensor_Data_Output .....	40
<b>Chapter 5. Messages for GestIC® Library Update</b>	
5.1 Library Loader Update Procedure .....	45
5.2 FwUpdateStart .....	46
5.3 FwUpdateStartPage .....	47
5.4 FwUpdateToBuffer .....	47
5.5 FwUpdateFlashBuffer .....	48
5.6 FwUpdateVerify .....	49
5.7 FwUpdateCompleted .....	50
<b>Appendix A. I<sup>2</sup>C Command Examples</b>	
<b>Appendix B. Glossary</b>	
<b>Worldwide Sales and Service .....</b>	<b>58</b>

---

---

## Preface

---

---

### NOTICE TO CUSTOMERS

All documentation becomes dated, and this manual is no exception. Microchip tools and documentation are constantly evolving to meet customer needs, so some actual dialogs and/or tool descriptions may differ from those in this document. Please refer to our website ([www.microchip.com](http://www.microchip.com)) to obtain the latest documentation available.

Documents are identified with a “DS” number. This number is located on the bottom of each page, in front of the page number. The numbering convention for the DS number is “DSXXXXA”, where “XXXX” is the document number and “A” is the revision level of the document.

For the most up-to-date information on development tools, see the MPLAB<sup>®</sup> IDE online help. Select the Help menu, and then Topics to open a list of available online help files.

## INTRODUCTION

This document applies exclusively to MGC3140 and MXG3141. If not differently stated, “GestIC<sup>®</sup>” is used to refer to both devices.

This chapter contains general information that will be useful to know before using the MGC3140/MXG3141 GestIC<sup>®</sup> Library Interface. Items discussed in this chapter include:

- Document Layout
- Conventions Used in this Guide
- Warranty Registration
- Recommended Reading
- The Microchip Website
- Development Systems Customer Change Notification Service
- Customer Support
- Document Revision History

## DOCUMENT LAYOUT

This document describes the MGC3140/MXG3141 GestIC Library and is organized as follows:

- [Chapter 1. Introduction](#)
- [Chapter 2. GestIC<sup>®</sup> Host Interface](#)
- [Chapter 3. GestIC<sup>®</sup> Library Message Interface](#)
- [Chapter 4. GestIC<sup>®</sup> Library Message Reference](#)
- [Chapter 5. Messages for GestIC<sup>®</sup> Library Update](#)
- [Appendix A. I<sup>2</sup>C Command Examples](#)
- [Appendix B. Glossary](#)

## CONVENTIONS USED IN THIS GUIDE

This manual uses the following documentation conventions:

### DOCUMENT CONVENTIONS

Description	Represents	Examples
<b>Arial font:</b>		
Italic characters	Referenced books	<i>MPLAB<sup>®</sup> IDE User's Guide</i>
	Emphasized text	...is the <i>only</i> compiler...
Initial caps	A window	the Output window
	A dialog	the Settings dialog
	A menu selection	select Enable Programmer
Quotes	A field name in a window or dialog	"Save project before build"
Underlined, italic text with right angle bracket	A menu path	<u><i>File&gt;Save</i></u>
Bold characters	A dialog button	Click <b>OK</b>
	A tab	Click the <b>Power</b> tab
N'Rnnnn	A number in verilog format, where N is the total number of digits, R is the radix and n is a digit.	4'b0010, 2'hF1
Text in angle brackets < >	A key on the keyboard	Press <Enter>, <F1>
<b>Courier New font:</b>		
Plain Courier New	Sample source code	<code>#define START</code>
	Filenames	<code>autoexec.bat</code>
	File paths	<code>c:\mcc18\h</code>
	Keywords	<code>_asm, _endasm, static</code>
	Command-line options	<code>-Opa+, -Opa-</code>
	Bit values	<code>0, 1</code>
	Constants	<code>0xFF, 'A'</code>
Italic Courier New	A variable argument	<i>file.o</i> , where <i>file</i> can be any valid filename
Square brackets [ ]	Optional arguments	<code>mcc18 [options] file [options]</code>
Curly brackets and pipe character: {   }	Choice of mutually exclusive arguments; an OR selection	<code>errorlevel {0 1}</code>
Ellipses...	Replaces repeated text	<code>var_name [, var_name...]</code>
	Represents code supplied by user	<code>void main (void) { ... }</code>

## WARRANTY REGISTRATION

Please complete the enclosed Warranty Registration Card and mail it promptly. Sending in the Warranty Registration Card entitles users to receive new product updates. Interim software releases are available at the Microchip website.

## RECOMMENDED READING

This user's guide describes how to use MGC3140 GestIC Library Interface. Other useful documents are listed below. The following Microchip documents are available and recommended as supplemental reference resources.

### **MGC3140 3D Tracking and Gesture Controller Data Sheet (40002037)**

Consult this document for information regarding the MGC3140 3D Tracking and Gesture Controller.

### **MXG3141 3D Gesture Controller Data Sheet (40001975)**

Consult this document for information regarding the MXG3141 3D Gesture Controller.

### **Aurea Graphical User Interface User's Guide**

Describes how to use the MGC3X30 Aurea Graphical User Interface.

### **GestIC® Design Guide (DS40001716)**

This document describes the GestIC system characteristic parameters and the design process. It enables the user to generate a good electrode design and to parameterize the full GestIC system.

### **Aurea Software Package – Aurea GUI and GestIC Library**

The Aurea GUI contains detailed information on GestIC library features and their parameterization. This information can be accessed via the help pages inside the Aurea parameterization wizard and can also be found as html documents in the Aurea installation folder '01\_ Documentation'.

## THE MICROCHIP WEBSITE

Microchip provides online support via our website at [www.microchip.com](http://www.microchip.com). This website is used as a means to make files and information easily available to customers. Information about GestIC technology and MGC3140 can be directly accessed via <http://www.microchip.com/gestic>.

## DEVELOPMENT SYSTEMS CUSTOMER CHANGE NOTIFICATION SERVICE

Microchip's customer notification service helps keep customers current on Microchip products. Subscribers will receive e-mail notification whenever there are changes, updates, revisions or errata related to a specified product family or development tool of interest.

To register, access the Microchip website at [www.microchip.com](http://www.microchip.com), click on Customer Change Notification and follow the registration instructions.

The Development Systems product group categories are:

- **Compilers** – The latest information on Microchip C compilers, assemblers, linkers and other language tools. These include all MPLAB<sup>®</sup> C compilers; all MPLAB assemblers (including MPASM<sup>™</sup> assembler); all MPLAB linkers (including MPLINK<sup>™</sup> object linker); and all MPLAB librarians (including MPLIB<sup>™</sup> object librarian).
- **Emulators** – The latest information on Microchip in-circuit emulators. This includes the MPLAB<sup>®</sup> REAL ICE<sup>™</sup> and MPLAB ICE 2000 in-circuit emulators.
- **In-Circuit Debuggers** – The latest information on the Microchip in-circuit debuggers. This includes MPLAB ICD 3 in-circuit debuggers and PICKit<sup>™</sup> 3 debug express.
- **MPLAB<sup>®</sup> IDE** – The latest information on Microchip MPLAB IDE, the Windows Integrated Development Environment for development systems tools. This list is focused on the MPLAB IDE, MPLAB IDE Project Manager, MPLAB Editor and MPLAB SIM simulator, as well as general editing and debugging features.
- **Programmers** – The latest information on Microchip programmers. These include production programmers such as MPLAB REAL ICE in-circuit emulator, MPLAB ICD 3 in-circuit debugger and MPLAB PM3 device programmers. Also included are nonproduction development programmers such as PICSTART<sup>®</sup> Plus and PICKit 2 and 3.



## CUSTOMER SUPPORT

Users of Microchip products can receive assistance through several channels:

- Distributor or Representative
- Local Sales Office
- Field Application Engineer (FAE)
- Technical Support

Customers should contact their distributor, representative or field application engineer (FAE) for support. Local sales offices are also available to help customers.

Technical support is available through the website at:

<http://www.microchip.com/support>.

## DOCUMENT REVISION HISTORY

### Revision C (March, 2021)

Updated Preface; Updated Section 1.1-1.3, 1.6, 2.1, 3.6.3, Section 4.4, and Section 4.5.3.1, 4.5.4.1, 4.5.5.1; Added new Section 4.5.4.2; Removed Section 1.4, 1.5, and 4.5.4.2; Removed UpdateFunction from CRC field description; Updated Table 4-3, 4-7, 4-10, 4-11, and Table A-2 and B-1; Updated Figure 1-1 and 3-1; Updated device name; Updated old terminology; Other minor corrections.

### Revision B (April, 2019)

Updated Table 5-2, Table 5-4, Table 5-8, Table 5-11, and Table 5-12.

Other minor corrections.

### Revision A (June, 2018)

Initial release of the document.

## Chapter 1. Introduction

### 1.1 PURPOSE OF THIS DOCUMENT

This document is the interface description of the GestIC<sup>®</sup> Library. It outlines the function of the Library's I<sup>2</sup>C message interface and contains the complete message reference to control and operate the GestIC system. The interface provides the capability to configure run-time parameters and read back gesture data, positional information and status. More detailed configuration can be performed on design time parameters using the Colibri suite.

The main sections covered are:


- Description of the message interface and data protocol
- Message reference of the GestIC Library

### 1.2 GESTIC<sup>®</sup> SOFTWARE ARCHITECTURE

A GestIC system can be accessed by I<sup>2</sup>C via the message interface of the GestIC Library.

Figure 1-1 shows the I<sup>2</sup>C access.

**FIGURE 1-1: GESTIC<sup>®</sup> SOFTWARE ACCESS**



**Note:** The same I<sup>2</sup>C interface is used for parameterization and host communication. For parameterization, a connector for the I<sup>2</sup>C bridge will be connected. The host must be disconnected or be set to high impedance during parameterization.

## 1.3 GestIC<sup>®</sup> LIBRARY


The GestIC Library is embedded firmware stored on the GestIC's internal Flash memory. It contains:

- The Colibri Suite with the digital signal processing algorithms for GestIC features (i.e., GestIC core features Approach Detection, Position Tracking and Gesture Recognition)
- The System Control block handling low-level functions and configuration storage
- The Library Loader for updates of the GestIC Library

The main building blocks are shown in [Figure 1-2](#).

The GestIC Library incorporates a message-based interface that allows the Configuration of the chip and the streaming of the sensor data to the host application.

**FIGURE 1-2: BUILDING BLOCKS OF GestIC<sup>®</sup> LIBRARY**



## 1.4 DEVICE SPECIFIC LIMITATIONS

**Note:** "Approach Detection", "Airwheel", and "Position Output Information" are supported on the device only if explicitly indicated in the associated hardware data sheet. Enabling these features on devices not supporting them could result in incorrect gesture detection and/or inaccurate position information.

---

---

## **Chapter 2. GestIC<sup>®</sup> Host Interface**

---

---

### **2.1 GESTIC<sup>®</sup> HARDWARE INTERFACE**

Communication with the GestIC is accomplished via a two-wire I<sup>2</sup>C-compatible serial port, supported by the TS and MCLR lines, so the user can read the sensor data and send control messages to the chip.

Refer to the GestIC data sheet for hardware details on the I<sup>2</sup>C interface.

## Chapter 3. GestIC® Library Message Interface

### 3.1 MESSAGES OVERVIEW

GestIC® Library messages are defined for providing sensor data to the host application and for controlling GestIC and its embedded features. They are sent as the payload of the I<sup>2</sup>C packets.

**TABLE 3-1: MESSAGES FOR SYSTEM CONTROL**

ID	Name	Page
0x40	Echo_Request	23
0x15	System_Status	23
0x06	Request_Message	27
0x83	Fw_Version_Info	28
0xA2	Set_Runtime_Parameter	31

**TABLE 3-2: MESSAGE FOR SENSOR DATA OUTPUT**

ID	Name	Page
0x91	Sensor_Data_Output	40


**TABLE 3-3: GESTIC® MESSAGES – BOOTLOADER DESCRIPTION**

ID	Name	Page
0x70	FwUpdateStart	46
0x71	FwUpdateStartPage	47
0x72	FwUpdateToBuffer	47
0x73	FwUpdateFlashBuffer	48
0x74	FwUpdateVerify	49
0x75	FwUpdateCompleted	50

### 3.2 MESSAGE FORMAT


A message is the container to exchange data between the GestIC Library and the application host. Each message has a minimum length of 4 bytes and a maximum of 255 bytes, and fits into the data packets of the communication interface (e.g., I<sup>2</sup>C). Each frame transports a single message (see [Figure 3-1](#)).

**FIGURE 3-1: MESSAGE EMBEDDED IN THE I<sup>2</sup>C FRAME**



A message consists always of a 4-byte header and a variable payload. The format is shown in [Figure 3-2](#).


**FIGURE 3-2: MESSAGE FORMAT**



## 3.3 MESSAGE HEADER

The GestIC Library message header is fixed and has a length of 4 bytes. It contains four data fields, as shown in [Figure 3-3](#) and explained in [Table 3-4](#).

**FIGURE 3-3: MESSAGE HEADER**




**TABLE 3-4: DATA FIELDS OF MESSAGE HEADER**

Field	Size (in bytes)	Description
Msg. Size	1	Complete size of the message in bytes including the header.
Flags	1	Reserved for future use.
Seq.	1	Sequence number which is increased for each message sent out by GestIC <sup>®</sup> . Range is 0...255. The host controller can use that information to verify if the messages got lost during I <sup>2</sup> C transmission. GestIC <sup>®</sup> ignores the sequence number in the received messages.
ID	1	ID of the message. For each ID, the GestIC <sup>®</sup> Library holds a dedicated structure containing the message direction, its payload elements and possible reply actions.

## 3.4 MESSAGE PAYLOAD

The message payload has a variable length and consists of one or more payload elements that contain the information to be exchanged. Depending on the content, these elements can be numerical values or dedicated numbers.

**FIGURE 3-4: MESSAGE PAYLOAD**



**Note:** Payload elements are exchanged in little-endian format. This means that the Lowest Significant Byte is written first.

Example: Element of 4 bytes: [Byte0]:[Byte1]:[Byte2]:[Byte3]

The structure and content of the payload elements is given in [Chapter 4. “GestIC<sup>®</sup> Library Message Reference”](#).

## 3.5 MESSAGE CODING AND DECODING

GestIC Library messages can be read as a row of hexadecimal values. In order to decode them, the header and payload elements need to be extracted and mapped to the definition in the message reference (see [Chapter 4. “GestIC<sup>®</sup> Library Message Reference”](#)).

As an example message, ID 0x91, `Sensor_Data_Output` is decoded in the following section.

### EXAMPLE 3-1: HEXADECIMAL REPRESENTATION OF MESSAGE 0x91

12 00 15 91 0E 01 EF 80 02 10 00 00 00 00 00 00 00
----------------------------------------------------

#### 3.5.1 Header Extraction

### EXAMPLE 3-2: MESSAGE HEADER

12 00 15 91 0E 01 EF 80 02 10 00 00 00 00 00 00 00
----------------------------------------------------

The message header contains the following information:

- Size: 0x12 Message including header has a length of 18 bytes
- Flags: 0x00 Flags are not set
- Seq.: 0x15 The message has been sent out with a sequence number of 21
- ID: 0x91 The message ID is 0x91, `Sensor_Data_Output`

## 3.5.2 Payload Extraction

### EXAMPLE 3-3: MESSAGE PAYLOAD

```
12 00 15 91 0E 01 EF 80 02 10 00 00 00 00 00 00 00
```

According to [Section 4.6 “Sensor\\_Data\\_Output”](#), the payload holds the following data:

- **DataOutputConfigMask** (2 bytes)

The value of ‘0x010E’ is the bit mask indicating what optional fields are included in the payload. The following bits are set in this example:

- Bit 1: A `GestureInfo` field is included in the payload.
- Bit 2: A `TouchInfo` field is included in the payload.
- Bit 3: The `AirWheelInfo` field is included in the payload.
- Bit 8 is set but it is one of the reserved bits and must be ignored.

As all other bits are not set, no `DSPStatus`, `xyzPosition`, `NoisePower`, `CICData` or `SDData` fields are included in the message.

- **TimeStamp** (1-byte)

Value ‘0xEF’ indicates that the event leading to this message occurred when the 200 Hz wrap-around counter was at value 239 (0xEF). This `TimeStamp` can be used to measure the time difference for events which did not occur too far apart in time (around one second).

- **SystemInfo** (1-byte)

Value ‘0x80’, which only the `DSPRunning` flag is set.

`PositionValid` is not set so there is either no hand in the electrical field or it is too far away.

`AirWheelValid` is not set, so even though there is an `AirWheelInfo` field included in the message, it should be ignored as currently the `AirWheel` gesture is not actively detected.

`RawDataValid`, `NoisePowerValid` are also not set, simply because the data is not included in the message.

The `EnvironmentalNoise` flag is not set, meaning that there is no external electrical interference which would reduce the performance of the sensor.

- **GestureInfo** (4-bytes)

This field has value ‘0x00001002’. So bits <7:0> have the value ‘0x02’ indicating a west to east flick has been performed. And bits <15:12> contain the value ‘0x1’ indicating that the gesture class was “*Flick gesture*”.

Bit 31 is ‘0’ meaning that the gesture has been completed. If it was ‘1’ it would have meant that the gesture recognition is still in progress.

- **TouchInfo** (4-bytes)

This field is all zeros in the example, which indicates that the user is not currently touching any electrode.

- **AirWheelInfo** (2-bytes)

The value is ‘0x0000’ as currently no `AirWheel` is in progress and the `AirWheelValid` flag in the `SystemInfo` field was ‘0’.



## 3.6 MESSAGE CONTROL FLOW AND CODING EXAMPLES

### 3.6.1 Message Control Flow


The control of the GestIC Library is done through the following messages:

- `Set_Runtime_Parameter` (ID 0xA2)
- `Request_Message` (ID 0x06)

The GestIC acknowledges each control message by a `System_Status` (ID 0x15), which contains the original message ID and a 2-byte error code. If the error code is '0', the message is applied correctly to GestIC.

The message control flow from the point of view of the application host is shown in Figure 3-5.

**FIGURE 3-5: APPLICATION HOST MESSAGE CONTROL**



**Note:** The Emerald I<sup>2</sup>C to USB bridge prefixes every I<sup>2</sup>C packet with 0xFE 0xFF before it is sent out via UART emulation on USB. That is done to allow a frame separation inside the data stream of the PC. For messages sent to GestIC<sup>®</sup> via the I<sup>2</sup>C to USB bridge from a terminal program (e.g., Hterm), the prefix has to be added as well.

---

### 3.6.2 Read GestIC® Library Version

After Power-on or Reset, GestIC runs the Library Loader and sends out the message `Fw_Version_Info` (0x83). The application host can receive this message as a first communication check. After a time-out of 200 ms, the GestIC Library Processing mode is started automatically.

The application host can request the FW\_Version\_Info during run time by using Request\_Message (0x06).

### 3.6.2.1 EXAMPLE: Request\_Fw\_Version INFO

The following example shows how the `Request_Message` (0x06) is used to request a `FW_Version_Info` (0x83) message.

**TABLE 3-5: MESSAGE FROM HOST TO MGC3140: REQUEST MESSAGE (0X06)**

Raw Message	0C 00 00 06 83 00 00 00 00 00 00 00		
Payload Element	MessageID	Reserved	Parameter
Hex in little-endian	83	00 00 00	00 00 00 00
Hex decoded	0x83	n/a	n/a
Description	FW_Version_Info	n/a	n/a

MGC3140 replies with message `FW_Version_Info` (0x83) followed by `System_Status` (0x15), containing the error code.

**TABLE 3-6: MESSAGE FROM MGC3140 TO HOST: FwVersionInfo (0X83)**

[illegible]

## 3.6.3 Run-Time Control

A dedicated set of run-time control options is provided within the message `Set_Runtime_Parameter` (0xA2). It can be used to control the active feature set and sensor data output and, thus, it allows the build-up of a context-sensitive operation of GestIC. For a detailed message description, refer to [Section 4.5 “Set\\_Runtime\\_Parameter”](#).

The following examples show how to set relevant run-time parameters.

### 3.6.3.1 EXAMPLE: ENABLE APPROACH DETECTION

This example shows how to enable the Approach Detection mode by using the message `Set_Runtime_Parameter` (0xA2). (Only on supported devices.)

**TABLE 3-7: MESSAGE FROM HOST TO MGC3140: SET\_RUNTIME\_PARAMETER (0xA2)**

Raw Message	10 00 00 A2 97 00 00 00 01 00 00 00 01 00 00 00			
Payload Element	RuntimeParameterID	Reserved	Argument0	Argument1
Hex in little-endian	97 00	00 00	01 00 00 00	01 00 00 00
Hex decoded	0x0097	n/a	0x00000001	0x00000001
Description	ApproachDetection	n/a	Enable Approach Detection mode	Mask for Approach Detection bit

MGC3140 replies with message `System_Status` (0x15), containing the error code.

**Note:** The Approach Detection mode is not available for MXG3141.

**TABLE 3-8: MESSAGE FROM MGC3140 TO HOST: SYSTEM\_STATUS (0x15)**

Raw Message	10 00 08 15 A2 34 00 00 00 00 00 00 00 00 00 00				
Payload Element	MsgID	MaxCmdSize	ErrorCode	Reserved	Reserved
Hex in little-endian	A2	34	00 00	00 00 00 00	00 00 00 00
Hex decoded	0xA2	0x34	0x0000	n/a	n/a
Description	Acknowledge to ID 0xA2	n/a	No error	n/a	n/a

### 3.6.3.2 EXAMPLE: ENABLE ALL GESTURES

This example shows how to enable all gestures (Flicks and Circles) by using the message `Set_Runtime_Parameter` (0xA2).

**TABLE 3-9: MESSAGE FROM HOST TO MGC3140: SET\_RUNTIME\_PARAMETER (0xA2)**

Raw Message	10 00 00 A2 85 00 00 00 7F 00 00 00 7F 00 00 00			
Payload Element	RuntimeParameterID	Reserved	Argument0	Argument1
Hex in little-endian	85 00	00 00	7F 00 00 00	7F 00 00 00
Hex decoded	0x0085	n/a	0x0000007F	0x0000007F
Description	despGestureMask	n/a	Enable gestures 0..6	Mask for Enable gestures 0..6 bits

MGC3140 replies with message `System_Status` (0x15). Refer to [Table 3-8](#).

## 3.6.3.3 EXAMPLE: ENABLE DATA OUTPUT

This example shows how to enable the sensor data output of Gesture Data, Touch Data, AirWheel Data and Position Data. Refer to [Section 4.5.5.4 “Data Output Enable Mask”](#).

**TABLE 3-10: MESSAGE FROM HOST TO MGC3140: SET RUNTIME PARAMETER (0xA2)**

Raw Message	10 00 00 A2 A0 00 00 00 1E 00 00 00 FF FF FF FF			
Payload Element	RuntimeParameterID	Reserved	Argument0	Argument1
Hex in little-endian	A0 00	00 00	1E 00 00 00	FF FF FF FF
Hex decoded	0x00A0	0x0000	0x0000001E	0xFFFFFFFF
Description	DataOutputEnableMask	n/a	Enable bit 1...bit 4; disable all other bits	Overwrite existing Configuration

MGC3140 replies with message `System_Status` (0x15). Refer to [Table 3-8](#).

## 3.6.3.4 EXAMPLE: LOCK DATA OUTPUT

This example shows how to lock the sensor data output of Gesture Data, Touch Data, AirWheel Data and Position Data. Refer to [Section 4.5.5.5 “Data Output Lock Mask”](#).

**TABLE 3-11: MESSAGE FROM HOST TO MGC3140: SET RUNTIME PARAMETER (0xA2)**

Raw Message	10 00 00 A2 A1 00 00 00 1E 00 00 00 FF FF FF FF			
Payload Element	RuntimeParameterID	Reserved	Argument0	Argument1
Hex in little-endian	A1 00	00 00	1E 00 00 00	FF FF FF FF
Hex decoded	0x00A1	0x0000	0x0000001E	0xFFFFFFFF
Description	DataOutputLockMask	n/a	Enable bit 1...bit 4; disable all other bits	Overwrite existing Configuration

MGC3140 replies with message `System_Status` (0x15). Refer to [Table 3-8](#).

## 3.6.4 Sensor Data Output

The GestIC Library processes sensor data with a default update rate of 5 ms. That means the I<sup>2</sup>C message buffer is regularly updated in that time interval. Whenever new data is available, GestIC pulls the TS line to request the I<sup>2</sup>C host to transfer this data. Sensor data sent from GestIC to the host are included in the message `Sensor_Data_Output` (0x91).

The content of the sensor data output can be configured via the message `Set_Runtime_Parameter` (0xA2).

### 3.6.4.1 EXAMPLE: READ SENSOR DATA OUTPUT

In the following examples the sensor data output is configured according to [Section 3.6.3.3 “Example: Enable Data Output”](#) and [Section 3.6.3.4 “Example: Lock Data Output”](#).

**TABLE 3-12: MESSAGE FROM MGC3140 TO HOST: FLICK EAST TO WEST**

Raw Message	18 08 FF 91 1E 01 57 8C 03 10 04 00 00 00 00 00 00 00 00 00 00 00 00 00 00																			
Payload Element	SystemInfo				GestureInfo				TouchInfo				Air-WheelInfo				xyzPosition			
Hex in little-endian	8C				03 10 04 00				00 00 00 00				00 00				00 00 00 00 00 00			
Hex decoded	0x8C				0x00041003				0x00000000				0x0000				0x000000000000			
Description	Bit 2: RawDataValid Bit 3: NoisePowerValid Bit 7: DSPRunning				Flick East to West				No touch				No AirWheel				No Position Data available			

**TABLE 3-13: MESSAGE FROM MGC3140 TO HOST: TOUCH OF CENTER ELECTRODE**

Raw Message	18 08 3B 91 1E 01 38 8D 00 00 00 00 10 00 00 00 00 00 5A A6 12 53 6B 0A														
Payload Element	SystemInfo	GestureInfo	TouchInfo	Air-WheelInfo	xyzPosition										
Hex in little-endian	8D	00 00 00 00	10 00 00 00	00 00	5A A6 12 53 6B 0A										
Hex decoded	0x8D	0x00000000	0x00000010	0x0000	Byte 1 and 2: 0xA65A Byte 3 and 4: 0x5312 Byte 5 and 6: 0x0A6B										
Description	Bit 0: PositionValid Bit 2: RawDataValid Bit 3: NoisePowerValid Bit 7: DSPRunning	No Gesture Detected	Touch on Center Electrode	No AirWheel Data	x: 42586 y: 21266 z: 2667										

# GestIC<sup>®</sup> Library Message Interface

**TABLE 3-14: MESSAGE FROM MGC3140 TO HOST: POSITION**

Raw Message	18 08 44 91 1E 01 41 8D 00 00 00 00 00 00 00 00 2F B2 E7 87 6A 35					
Payload Element	SystemInfo	GestureInfo	TouchInfo	Air-WheelInfo	xyzPosition	
Hex in little-endian	8D	00 00 00 00	00 00 00 00	00 00	2F B2 E7 87 6A 35	
Hex decoded	0x8D	0x00000000	0x00000000	0x0000	Byte 1 and 2: 0xB22F Byte 3 and 4: 0x87E7 Byte 5 and 6: 0x356a	
Description	Bit 0: PositionValid Bit 2: RawDataValid Bit 3: NoisePowerValid Bit 7: DSPRunning	No Gesture Detected	Touch on Center Electrode	No AirWheel Data	x: 45615 y: 34791 z: 13674	

## Chapter 4. GestIC<sup>®</sup> Library Message Reference

### 4.1 ECHO\_REQUEST

When the `Echo_Request` message is sent to the chip, GestIC will reply with the same content. Message length and content can be chosen by the user. For a correct communication, the total length of the sent message must be entered in the size field of the message header. The sequence looks like the following:

- Sent: 0A 00 00 40 01 02 03 04 05 06
- Reply: 0A 00 68 40 01 02 03 04 05 06

Direction: Host to GestIC, reply GestIC to Host

**TABLE 4-1: ECHO\_REQUEST MESSAGE OVERVIEW**

Header				Payload
Msg. Size	Flags	Seq.	ID	User-defined content
1 Byte	1 Byte	1 Byte	1 Byte	n/a
n/a	n/a	n/a	0x40	Zero or more octets of arbitrary data

### 4.2 SYSTEM\_STATUS

`System_Status` is used to acknowledge the reception of messages from the host. This message holds the error code and is used to confirm the transmission of the following messages:

- [Request\\_Message](#)
- [Set\\_Runtime\\_Parameter](#)
- [FwUpdateStart](#)
- [FwUpdateStartPage](#)
- [FwUpdateToBuffer](#)
- [FwUpdateFlashBuffer](#)
- [FwUpdateVerify](#)
- [FwUpdateCompleted](#)

The message format has been changed compared to MGC3x30 variants.

Direction: GestIC to Host

**TABLE 4-2: MESSAGE OVERVIEW**

Header				Payload						
Msg. Size	Flags	Seq	ID	MsgId	MaxCmdSize	ErrorCode	Reserved1	Flags	SeqCtr	Reserved2
1 Byte	1 Byte	1 Byte	1 Byte	1 Byte	1 Byte	2 Bytes	2 Bytes	1 Byte	1 Byte	4 Bytes
0x10	n/a	n/a	0x15	see description below						

**TABLE 4-3: PAYLOAD ELEMENTS**

Element	Size	Description																														
MsgId	1	If the status message is in response to a command from the host, then the <code>MsgId</code> (including message header) is accepted by the firmware																														
MaxCmdSize	1	Maximum allowed message size which the firmware will accept																														
ErrorCode	2	<p>Error code, referring to the last received message  <b>Structure:</b> 16-bit Word containing dedicated values (see list below)  <b>Possible Values:</b></p> <p>These error codes are sent by the Library Loader, Library Loader Updater and Library:</p> <table> <tr> <td>0x0000</td> <td>NoError</td> <td>OK</td> </tr> <tr> <td>0x0001</td> <td>UnknownCommand</td> <td>The <code>MsgId</code> is unknown</td> </tr> </table> <p>These error codes are sent by the Library Loader:</p> <table> <tr> <td>0x0002</td> <td>InvalidSessionId</td> <td>Session ID is invalid or does not match (0x0 is not allowed) (message <code>FwUpdateStart</code>, <code>FwUpdateCompleted</code>)</td> </tr> <tr> <td>0x0003</td> <td>InvalidMsgCrc</td> <td>CRC of the current message is invalid, (message <code>FwUpdateBlock</code>, <code>FwUpdateStart</code>, <code>FwUpdateCompleted</code>)</td> </tr> <tr> <td>0x0004</td> <td>InvalidLength</td> <td>Length is invalid (message <code>FwUpdateBlock</code>)</td> </tr> <tr> <td>0x0005</td> <td>InvalidAddress</td> <td>Address is invalid (message <code>FwUpdatedBlock</code>)</td> </tr> <tr> <td>0x0006</td> <td>InvalidFunction</td> <td>Function ID is invalid (message <code>FwUpdateStart</code>, <code>FwUpdatedBlock</code>)</td> </tr> <tr> <td>0x0008</td> <td>ContentMismatch</td> <td>VerifyOnly function found a mismatch between content and Flash memory (message <code>FwUpdateBlock</code>)</td> </tr> <tr> <td>0x0009</td> <td>NoClientReachable</td> <td>A client is not available, or communication is lost</td> </tr> <tr> <td>0x000A</td> <td>NoFwPresent</td> <td>No valid <code>Fw</code> is present to execute</td> </tr> </table>	0x0000	NoError	OK	0x0001	UnknownCommand	The <code>MsgId</code> is unknown	0x0002	InvalidSessionId	Session ID is invalid or does not match (0x0 is not allowed) (message <code>FwUpdateStart</code> , <code>FwUpdateCompleted</code> )	0x0003	InvalidMsgCrc	CRC of the current message is invalid, (message <code>FwUpdateBlock</code> , <code>FwUpdateStart</code> , <code>FwUpdateCompleted</code> )	0x0004	InvalidLength	Length is invalid (message <code>FwUpdateBlock</code> )	0x0005	InvalidAddress	Address is invalid (message <code>FwUpdatedBlock</code> )	0x0006	InvalidFunction	Function ID is invalid (message <code>FwUpdateStart</code> , <code>FwUpdatedBlock</code> )	0x0008	ContentMismatch	VerifyOnly function found a mismatch between content and Flash memory (message <code>FwUpdateBlock</code> )	0x0009	NoClientReachable	A client is not available, or communication is lost	0x000A	NoFwPresent	No valid <code>Fw</code> is present to execute
0x0000	NoError	OK																														
0x0001	UnknownCommand	The <code>MsgId</code> is unknown																														
0x0002	InvalidSessionId	Session ID is invalid or does not match (0x0 is not allowed) (message <code>FwUpdateStart</code> , <code>FwUpdateCompleted</code> )																														
0x0003	InvalidMsgCrc	CRC of the current message is invalid, (message <code>FwUpdateBlock</code> , <code>FwUpdateStart</code> , <code>FwUpdateCompleted</code> )																														
0x0004	InvalidLength	Length is invalid (message <code>FwUpdateBlock</code> )																														
0x0005	InvalidAddress	Address is invalid (message <code>FwUpdatedBlock</code> )																														
0x0006	InvalidFunction	Function ID is invalid (message <code>FwUpdateStart</code> , <code>FwUpdatedBlock</code> )																														
0x0008	ContentMismatch	VerifyOnly function found a mismatch between content and Flash memory (message <code>FwUpdateBlock</code> )																														
0x0009	NoClientReachable	A client is not available, or communication is lost																														
0x000A	NoFwPresent	No valid <code>Fw</code> is present to execute																														



# GestIC<sup>®</sup> Library Message Reference

**TABLE 4-3: PAYLOAD ELEMENTS (CONTINUED)**

Element	Size	Description
ErrorCode	2	0x000B WrongParameterAddr Parameter address does not match Bootloader assumption
		0x000C WrongChip Parameter address does not match Bootloader assumption
		0x000D InvalidBufferCrc CRC of the page buffer is invalid, (message FwUpdateFlashBuffer)
		0x000E DataTooLong Data too long, FwUpdateToBuffer exceeds buffer size
		0x000F SessionInitFailed Failed to initialize session (message FwUpdateStart)
		0x0010 VerifyOK Verify OK (message: FwUpdateVerify)
		0x0011 UnpermittedOperation Unpermitted operation over the current page MsgIdFwUpdateFlashBuffer on FwInfo Page
		These error codes are sent by the Library:
		0x0014 WrongParameterValue Value of the Argument/Parameter of a RuntimeParameter command is out of the valid range (message: Request_Message and Set_Runtime_Parameter)
		0x0015 UnknownParameterID MsgId or RuntimeParameterId is unknown or out of the valid range (message: Request_Message and Set_Runtime_Parameter)
		0x0016 CompareAfterProgrammingFailed Compare After Flash Programming Failed
		0x001A WakeupHappened A wake-up by Host was detected
		These error codes are sent by the Library Loader Updater:
		0x0080 LoaderUpdateStarted Bootloader update started
		0x0081 LoaderUpdateFinished Bootloader update finished
		0x0082 LoaderUpdateFailed Bootloader update failed
		0x008E WrongChipID Chip ID wrong for update
		0x008F CommandTooShort Command too short
		0x0090 BadChecksum I <sup>2</sup> C checksum error
		0x0091 BadAppChecksum App checksum error
		0x0092 FlashPageNotEmptyAfterErase Flash page not empty after erase
		0x0093 FlashPageMismatchAfterWrite Flash page mismatch after write
		0x0094 FlashEraseRangesNotSupported Flash erase ranges not supported

**TABLE 4-3: PAYLOAD ELEMENTS (CONTINUED)**

Element	Size	Description
Reserved1	2	Reserved for future use
Flags	1	Copy of the flags field from the header of the last received message
SeqCtr	1	Copy of the sequence counter field from the header of the last received message
Reserved2	4	Reserved for future use

## 4.3 REQUEST\_MESSAGE

`Request_Message` forces GestIC Library to reply to the message with the requested ID.  
Direction: Host to GestIC

**TABLE 4-4: MESSAGE OVERVIEW**

Header				Payload		
Msg. Size	Flags	Seq.	ID	MessageID	Reserved	Param.
1 Byte	1 Byte	1 Byte	1 Byte	1 Byte	3 Bytes	4 Bytes
0x0C	n/a	n/a	0x06	Refer to <a href="#">Table 4-5</a>		

**TABLE 4-5: PAYLOAD ELEMENTS**

Element	Size (bytes)	Description
MessageID	1	Request the Message with ID, MessageID, from GestIC <sup>®</sup> Library. GestIC <sup>®</sup> Library will answer with the requested message or stay silent. <b>Structure:</b> Single-byte read as a hexadecimal value <b>Range:</b> (0x00...0xFF)
Reserved	3	Reserved, write as '0'.
Param.	4	Optional, parameter can be used to specify the kind of return. Example: Requesting message <code>SetRuntimeParameter</code> , Param. specifies the <code>RuntimeParameterId</code> to read back the parameter. <b>Structure:</b> 32-bit Word, containing dedicated values or bit fields. <b>Range:</b> (0x00000000...0xFFFFFFFF)

- Note 1:** The `Request_Message` command can only be used with MessageID 0x83 and 0xA2.
- 2:** The `TransFreqSelect` run-time parameter is a write-only parameter and cannot be requested with message `Request_Message`.
- 3:** For examples of the `Request_Message` command, refer to [Table A-1](#).

## 4.4 FW\_VERSION\_INFO

The `FirmwareVersion` message contains detailed version information for GestIC bootloader, firmware and parameterization. The message format has been changed compared to MGC3x30 variants. MGC3140/MXG3141 will transmit this message after a Reset.

Direction: MGC3140/MXG3141 to Host.

**TABLE 4-6: MESSAGE OVERVIEW**

Header				Payload										
Msg. Size	Flags	Seq.	ID	FwValid	HwRev	ParameterPage	BootloaderMinor	BootloaderMajor	ChipId	FirmwareStartPage	VersionString	CustomString	NewStructIndicator	FwInfoMajor
1 Byte	1 Byte	1 Byte	1 Byte	1 Byte	2 Bytes	1 Byte	1 Byte	1 Byte	1 Byte	1 Byte	9 Bytes	16 Bytes	3 Bytes	1 Byte
0x84	n/a	n/a	0x83	Refer to <a href="#">Table 4-7</a>										

Payload														
FwInfoMinor	FwMajor	FwMinor	FwRev	Padding0	CommitDistance	RcFwType	RcFwFlags	RcFwGitHash	RcDspType	RcDspFlags	RcDspPad0	RcDspRevision	RcDspPad1	BiEpoch
1 Byte	1 Byte	1 Byte	1 Byte	1 Byte	2 Bytes	1 Byte	1 Byte	14 Bytes	1 Byte	1 Bytes	2 Bytes	4 Bytes	8 Bytes	4 Byte
Refer to <a href="#">Table 4-7</a>														

Payload									
BiFlags	BiUserId	BiPadding	SysClkKHz	IdDspId	IdParameterId	IdApplicationId	IdAppDetail	PadToBootInfo	Reserved
1 Byte	1 Byte	2 Bytes	4 Bytes	2 Bytes	2 Bytes	2 Bytes	2 Bytes	12 Bytes	20 Bytes
Refer to <a href="#">Table 4-7</a>									

**TABLE 4-7: PAYLOAD ELEMENTS**

Element	Size (bytes)	Description
FwValid	1	This field indicates if the firmware in Flash is valid or somehow corrupted. All values different from the defined should be treated as invalid. <b>Possible values:</b> <div> <div>0x00</div> <div>Empty0</div> <div>No complete firmware image on the device</div> </div> <div> <div>0x0A</div> <div>InvalidFw</div> <div>Firmware on-chip is invalid. Indicates a started update that has been interrupted</div> </div> <div> <div>0xAA</div> <div>ValidFw</div> <div>A valid complete image is stored in the device Flash</div> </div> <div> <div>0xFF</div> <div>Empty1</div> <div>No complete firmware image on device</div> </div>
HwRev	2	Hardware revision
ParameterPage	1	First Flash page of the parameter section
BootloaderMinor	1	Bootloader version, minor digit <sup>(1)</sup>
BootloaderMajor	1	Bootloader version, major digit <sup>(1)</sup>
ChipId	1	Identifies the device on which this firmware runs <b>Possible values:</b> <div> <div>0x14</div> <div>Sabrewing</div> <div>Device is a 3130 (Sabrewing V1.0 variant)</div> </div> <div> <div>0x15</div> <div>Hillstar</div> <div>Device is a 3130 (Hillstar variant)</div> </div> <div> <div>0x32</div> <div>Woodstar</div> <div>Device is a 3030 (Woodstar variant)</div> </div> <div> <div>0x41</div> <div>3140</div> <div>Device is a 3140 (Emerald variant)</div> </div> <div> <div>0x42</div> <div>3141</div> <div>Device is a 3141 (2D/3D)</div> </div>
FirmwareStartPage	1	Page containing the firmware entry point.
VersionString	9	Version in format 'major.minor.rev' as string, filled with ';' until the 9 characters are full.
CustomString	16	16 characters for customer usage. If the string is shorter than 16 characters it must be filled with spaces. Entries defined by Microchip start with 'MCHP:'
NewStructIndicator	3	Contains the three character sequence {';', '!', '\0'} which is used to indicate that the firmware version info conforms to the format described here.
FwInfoMajor	1	Major version of this FirmwareVersion message structure. To confirm with this description it must be '1'.
FwInfoMinor	1	Minor version of this FirmwareVersion message structure. To confirm with this description it must be '0'.
FwMajor	1	8-bit integer containing the 'major' field of firmware version (firmware version is in format 'major.minor.rev').
FwMinor	1	8-bit integer containing the 'minor' field of firmware version (firmware version is in format 'major.minor.rev').
FwRev	1	8-bit integer containing the 'Rev' field of firmware version (firmware version is in format 'major.minor.rev').
Padding0	1	Reserved field, used to align the following field properly.
CommitDistance	2	Internal version information, describes how many commits we are away from the last set version tag in the VCS.
RcFwType	1	Revision control type of firmware, always '2' as GestIC <sup>®</sup> sources use 'Git'.
RcFwFlags	1	Revision control info for firmware: 'Flags' field. Bit 0 indicates that the sources were modified when compiling; Bit 1 indicates that the compile was from multiple mixed revisions.
RcFwGitHash	14	Revision control info for firmware: First 14 bytes of git hash for firmware.
RcDspType	1	Revision control type of DSP, always '1' as DSP sources use SVN.
RcDspFlags	1	Revision control info for DSP: 'Flags' field. Bit 0 indicates that the sources were modified when compiling; Bit 1 indicates that the compile was from multiple mixed revisions.

# GestIC<sup>®</sup> Library Message Reference

**TABLE 4-7: PAYLOAD ELEMENTS (CONTINUED)**

Element	Size (bytes)	Description
RcDspPad0	2	Revision control info for DSP: Padding to align next field containing the SVN revision.
RcDspRevision	4	Revision control info for DSP: Revision number from SVN.
RcDspPad1	8	Revision control info for DSP: Another 8 bytes of padding to fill generic revision info structure.
BiEpoch	4	BuildInfo: Build time UTC in 'epoch' format.
BiFlags	1	BuildInfo: Flags, if Bit 0 is set the user who builds the file is known and the 'UserId BuildInfo' field contains a valid value.
BiUserId	1	BuildInfo: Numeric ID identifying the user who build this firmware.
BiPadding	2	BuildInfo: Pad build info length to 8 bytes. Reserved for future use.
SysClkHz	4	System clock in Hz.
IdDspId	2	ID: DSP id field (900x = MGC3130, 910x = MGC3030, 45 = Sabrewing, 440x = MGC3140, 45xx = MXG3141).
IdParameterId	2	ID: Parameter Id can be used to identify different parameterizations.
IdApplicationId	2	ID: Application Id can be used to differentiate different applications. Currently only '0' (regular FW) and '1' (bootloader updater) are defined.
IdAppDetail	2	ID: 'appDetail' is currently a reserved field for future use. Must be '0'.
PadToBootInfo	12	Currently reserved bytes, used to pad until start of 'BootInfo' information.
Reserved	20	Reserved for future use.

**Note 1:** The current bootloader version is only contained when the message is "self-emitted" after Reset. When the message is requested by `Request_Message`, the bootloader version is always reported 0.0.

## 4.5 SET\_RUNTIME\_PARAMETER

This message is used to set run-time parameters within the GestIC Library. It supports parameters for AFE parameterization, feature Configuration, and sensor data output. A special value is defined for a persistent saving of parameters to the Flash memory. Parameters which can be made persistent are grouped into three categories:

- **Analog Front-End (AFE) Category**
- **Digital Signal Processing (DSP) Category**
- **System Category**

Direction: Host to GestIC

**TABLE 4-8: MESSAGE OVERVIEW**

Header				Payload			
Msg. Size	Flags	Seq.	ID	RuntimeParameterID	Reserved	Argument0	Argument1
1 Byte	1 Byte	1 Byte	1 Byte	2 Bytes	2 Bytes	4 Bytes	4 Bytes
0x10	n/a	n/a	0xA2	see description below			

**TABLE 4-9: PAYLOAD ELEMENTS**

Element	Element Size (bytes)	Description
RuntimeParameterID	2	ID of run-time parameter. Refer to <a href="#">Section 4.5.1 “Trigger”</a> through <a href="#">Section 4.5.5.5 “Data Output Lock Mask”</a> . <b>Structure:</b> 16-bit Word interpreted as hex value <b>Range:</b> (0x0000...0xFFFF)
Reserved	2	Write as '0'
Argument0	4	Argument values, depending on run-time parameter ID. If not used, Argument0 should be provided as '0'. <b>Structure:</b> 32-bit Word: Argument0 <b>Range:</b> depends on run-time parameter
Argument1	4	Argument values, depending on run-time parameter ID. If not used, Argument1 should be provided as '0'. <b>Structure:</b> 32-bit Word: Argument1 <b>Range:</b> depends on run-time parameter

## 4.5.1 Trigger

This parameter forces a trigger defined in `Argument0`.

RuntimeParameterID	0x1000	Trigger: Parameter forces a trigger
Argument0	0x00000000:	Force re-calibration
	0x00000002:	Enter Deep Sleep 1: The wake-up sources from Deep Sleep 1 are I <sup>2</sup> C0 Start bit detection or MCLR Reset. The system will resume from Deep Sleep on any I <sup>2</sup> C messages sent on the bus, and the first I <sup>2</sup> C message will be lost.
		<b>Range:</b> (0x00000000, 0x00000002)
Argument1	Not used	

## 4.5.2 Make Persistent

Use this ID to make the parameter set defined in `Argument0` persistent (store to Flash memory).

RuntimeParameterID	0xFF00	MakePersistent: Stores parameter in Flash
Argument0	0x00000000:	Store RTPs for AFE Category
	0x00000001:	Store RTPs for DSP Category
	0x00000002:	Store RTPs for System Category
		<b>Range:</b> (0x00000000, 0x00000001, 00000002)
Argument1	Not used	



## 4.5.3 Analog Front-End (AFE) Category

### 4.5.3.1 ELECTRODE MAPPING

Electrode mapping indicates what physical channel is used for a given logical electrode.

There are five “RuntimeParameterID” that can be associated to any of the five physical receive channels (device “RXn” pins).

Depending on how the device has been configured, electrodes can be intended in Frame mode or 4 South + 1 North mode.

Refer to the device hardware data sheet for a description of the available styles and for the location of the RX pins on the chosen package.

**TABLE 4-10: ELECTRODES MAPPING TO RUNTIMEPARAMETERID**

RuntimeParameterID	Electrode Name	
Value	Frame Style	4S + N Style
0x65	South	S1
0x66	West	S2
0x67	North	S3
0x68	East	S4
0x69	Center	N

Argument0 Contains the number of physical receive channels (Rx0, Rx1, Rx2, Rx3, Rx4)

**Range:** (0x00000000, 0x00000001, 0x00000002, 0x00000003, 0x00000004)

Argument1 Not used

## 4.5.4 Digital Signal Processing (DSP) Category

### 4.5.4.1 TRANSMIT FREQUENCY SELECTION

This sets the total number of transmitter frequencies used, and the order in which they are tested for the frequency hopping.

RuntimeParameterID 0x82 TransFreqSelect: Parameter to set the frequency IDs used

Argument0 Total number of used Tx frequencies.  
This parameter can be 1, 2, 3, 4 or 5.

Argument1 This determines in what order the transmitter frequencies are tested. The indexes are numbered 0 to 4 and represent respective transmitter frequencies.  
For MXG3141, the default frequencies are 44 kHz and 64/65/66/67 kHz.

Example: e.g., Argument0 = 0x04 in combination with  
Argument1 = 0x3104 means that frequencies with the index 4, 0, 1 and 3 are used and tested in this specific order.  
e.g., Index – Default Frequency Mapping  
(Argument 0 = 0x5, Argument 1 = 0x43210)

**Note:** The TransFreqSelect run-time parameter is a write-only parameter and could not be requested with REQUEST\_MESSAGE (0x06) message.

The active frequency is reported in the SensorDataOutput element 'DSPStatus' whenever the frequency changes.

### 4.5.4.2 TOUCH DETECTION

This parameter enables/disables Touch Detection.

RuntimeParameterID 0x97 dspTouchConfig: Parameter to enable/disable Touch Detection

Argument0 Set Argument0 to '0x08' to enable Touch Detection  
Set Argument0 to '0x00' to disable Touch Detection  
**Note:** If Argument1 is not set correctly, the system will show malfunctions.

Argument1 0x08

### 4.5.4.3 APPROACH DETECTION

This parameter enables/disables Approach Detection mode. (Only on supported devices.)

RuntimeParameterID 0x97 dspApproachDetectionMode: Parameter to enable/ disable Approach Detection Mode

Argument0 Set Argument0 to 0x01 to enable Approach Detection  
Set Argument0 to 0x00 to disable Approach Detection  
**Note:** If Argument1 is not set correctly, the system will show malfunctions.

Argument1 0x01

**Note:** The Approach Detection mode is not available for MXG3141.

## 4.5.5 System Category

### 4.5.5.1 AIRWHEEL

This parameter enables/disables AirWheel. (Only on supported devices.)

RuntimeParameterID	0x90	dspAirWheelConfig: Parameter to enable/disable AirWheel
Argument0		Set Argument0 to '0x20' to enable AirWheel Set Argument0 to '0x00' to disable AirWheel <b>Note:</b> If Argument1 is not set correctly, the system will show malfunctions.
Argument1	0x20	

**Note:** AirWheel is not supported by MXG3141.

### 4.5.5.2 GESTURE PROCESSING (HMM)

This parameter enables the in-built gestures. Disabling one gesture will increase the recognition probability of the others.

If a bit in Argument0 is set to '1', the respective Gesture will be enabled. If a bit in Argument0 is set to '0', the respective Gesture will be disabled.

RuntimeParameterID	0x85	dspGestureMask: Parameter to enable/disable gestures
Argument0		Bit 0: Garbage model Bit 1: Flick West to East Bit 2: Flick East to West Bit 3: Flick South to North Bit 4: Flick North to South Bit 5: Circle clockwise Bit 6: Circle counterclockwise Bit 7: Reserved Bit 8: Reserved Bit 22: Hold gesture Bit 23: Presence gesture Bit 24: Edge Flick West to East Bit 25: Edge Flick East to West Bit 26: Edge Flick South to North Bit 27: Edge Flick North to South Bit 28: Double Flick West to East Bit 29: Double Flick East to West Bit 30: Double Flick South to North Bit 31: Double Flick North to South
Argument1		Acts as a mask, set appropriate bits to '1' to change the flag. All other flags remain unchanged.

**Note:** Circle and Double Flick are not supported by MXG3141.

## 4.5.5.3 CALIBRATION OPERATION MODE

This parameter enables/disables the selected auto-calibration feature.

If a bit in `Argument0` is set to '0', the respective auto-calibration feature will be enabled.

If a bit in `Argument0` is set to '1' the respective auto-calibration feature will be disabled.

<code>RuntimeParameterID 0x80</code>	<code>dspCalOpMode</code> : Parameter to enable/disable auto-calibration
<code>Argument0</code>	Bit 1: Enable/disable gesture-triggered calibration Bit 2: Enable/disable negative calibration Bit 3: Enable/disable idle calibration Bit 4: Enable/disable invalidity value calibration, if values are completely out of range Bit 5: Enable/disable calibration triggered by AFA
<code>Argument1</code>	Acts as a mask, set appropriate bits to '1' to change the flag. All other flags remain unchanged.

## 4.5.5.4 DATA OUTPUT ENABLE MASK

This parameter determines the data output of the message `Sensor_Data_Output (0x91)`. If a bit in `Argument0` is set to '1', the respective payload element will be part of the message `Sensor_Data_Output (0x91)`. If a bit in `Argument0` is set to '0', the payload element will not be part of the message `Sensor_Data_Output (0x91)` when the data is updated (payload element is 'Off').

Use `DataOutputEnableMask` to optimize the sensor data output in terms of I<sup>2</sup>C utilization and efficiency of the host code.

**Note:** Enabling all payload elements might lead to malfunctions due to bandwidth limitations on the I<sup>2</sup>C bus.

<code>RuntimeParameterID</code>	<code>0xA0</code> <code>DataOutputEnableMask</code> : Parameter determining the data output
<code>Argument0</code>	<p>Bits 0...12: Payload elements: If set to '1', payload elements will be part of the message</p> <ul style="list-style-type: none"><li>Bit 0: DSP Status</li><li>Bit 1: Gesture Data</li><li>Bit 2: TouchInfo</li><li>Bit 3: AirWheelInfo</li><li>Bit 4: xyzPosition</li><li>Bit 5: Noise Power</li><li>Bit 6...10: These bits are reserved and must be set to '0'</li><li>Bit 11: CICData (Uncalibrated Signal)</li><li>Bit 12: SDData (Signal Deviation)</li></ul> <p>Bits 13...15: These bits are reserved and must be set to '0'</p> <p>Bits 16...17: SystemInfo Status bits: If set to '1', the reporting of a state change in the payload element SystemInfo is enabled</p> <ul style="list-style-type: none"><li>Bit 16: EnvironmentalNoise indication</li><li>Bit 17: Clipping indication<sup>(1)</sup></li></ul> <p>Bit 18: DSP running</p> <p>Bits 19: AirWheelCounterDecimation: If set to '1', the AirWheel counter is decimated by the factor of 4</p> <p>Bit 20: TimeStampOverflow: This applies when AirWheel or Touch Detection is ongoing. If activated, a message will be sent when the counter in the payload element TimeStamp is overflowing (TimeStamp=0)</p> <p>Bits 21...26: These bits are reserved</p> <p>Bits 27...31: GesturesInfo Status bits: If set to '1', the reporting of a state change in the payload element GestureInfo is enabled.</p> <ul style="list-style-type: none"><li>Bit 27: HandPresence flag</li><li>Bit 28: HandHold flag</li><li>Bit 29: HandInside flag</li></ul> <p>Bit 30: This bit is reserved</p> <p>Bit 31: GestureInProgress flag</p>
<code>Argument1</code>	Acts as a mask, set appropriate bits to '1' to change the flag. All other flags remain unchanged.

**Note 1:** Clipping indication is not supported by MGC3140/MXG3141. Message is kept for compliance with MGC3x30

## 4.5.5.5 DATA OUTPUT LOCK MASK

This parameter determines the data output of the `Sensor_Data_Output` (0x91) message. If a bit in `Argument0` is set to '1', the respective payload element will be part of the `Sensor_Data_Output` (0x91) message, no matter whether there is new data or not (payload element is 'On').

If a bit in `Argument0` is set to '0', the payload element will only be part of the message `Sensor_Data_Output` (0x91) when the data is updated (payload element is 'Dynamic').

RuntimeParameterID	0xA1	DataOutputLockMask: Parameter determining the data output
Argument0	Bits 0...12: Payload elements: If set to '1', payload elements will be part of the message	
	Bit 0: DSP Status	
	Bit 1: Gesture Data	
	Bit 2: TouchInfo	
	Bit 3: AirWheelInfo	
	Bit 4: xyzPosition	
	Bit 5: Noise Power	
	Bit 6...10: These bits are reserved and must be set to '0'.	
	Bit 11: CICData (Uncalibrated Signal)	
	Bit 12: SDData (Signal Deviation)	
	Bits 13...15: These bits are reserved and must be set to '0'	
Argument1	Acts as a mask, set appropriate bits to '1' to change the flag. All other flags remain unchanged.	

## 4.5.5.6 DATA OUTPUT REQUEST MASK

This parameter determines the data output only of the next message `Sensor_Data_Output (0x91)`. If a bit in `Argument0` is set to '1', the respective payload element will be part of the next message `Sensor_Data_Output (0x91)`.

If a bit in `Argument0` is set to '0', the payload element will not be part of the next message `Sensor_Data_Output (0x91)` when the data is updated.

This will force the GestIC to send a new message `Sensor_Data_Output (0x91)` even if there were no valid events and data. This message will contain data according to the `Argument0` selection. Then the `Sensor_Data_Output (0x91)` will be sent according to the Data Output Enable and Lock masks only on valid events and data.

RuntimeParameterID	0xA2	DataOutputRequestMask: Parameter determining the next data output
Argument0	Bits 0...12: Payload elements: If set to '1', payload elements will be part of the message	
	Bit 0: DSP Status	
	Bit 1: Gesture Data	
	Bit 2: TouchInfo	
	Bit 3: AirWheelInfo	
	Bit 4: xyzPosition	
	Bit 5: Noise Power	
	Bit 6...10: These bits are reserved and must be set to '0'.	
	Bit 11: CICData (Uncalibrated Signal)	
	Bit 12: SDData (Signal Deviation)	
	Bits 13...15: These bits are reserved and must be set to '0'	
Argument1	Acts as a mask, set appropriate bits to '1' to change the flag. All other flags remain unchanged.	

<p><b>Note:</b> For instances of the <code>Set_Runtime_Parameter</code> command examples, refer to <a href="#">Table A-2</a>.</p>
-----------------------------------------------------------------------------------------------------------------------------------

## 4.6 SENSOR\_DATA\_OUTPUT

This message contains the sensor data output of the GestIC. The content of the message can be configured via bit mask (refer to `DataOutputEnableMask` and `DataOutputLockMask` in [Section 4.5 “Set\\_Runtime\\_Parameter”](#)).

The elements `DataOutputConfigMask`, `TimeStamp`, and `SystemInfo` are always part of the message. The inclusion of further payload elements depends on the Configuration, and the actual Configuration can be read from the payload element `DataOutputConfigMask`.

Direction: GestIC to Host

**TABLE 4-11: MESSAGE OVERVIEW**

Header				Payload			
Size	Flags	Seq.	ID	<code>DataOutputConfigMask</code>	<code>TimeStamp</code>	<code>SystemInfo</code>	Variable depending on <code>DataOutputConfigMask</code>
1 Byte	1 Byte	1 Byte	1 Byte	2 Bytes	1 Byte	1 Byte	Variable depending on <code>DataOutputConfigMask</code>
variable	n/a	n/a	0x91	see description below			

**TABLE 4-12: PAYLOAD ELEMENTS**

Element	Element size (bytes)	Description
<code>DataOutputConfigMask</code>	2	<p>Bit mask indicating which data is part of the message. The following bits are used:</p> <ul style="list-style-type: none"> <li>Bit 0: <code>DSPStatus</code> field.</li> <li>Bit 1: <code>GestureInfo</code> field.</li> <li>Bit 2: <code>TouchInfo</code> field.</li> <li>Bit 3: <code>AirWheelInfo</code> field.</li> <li>Bit 4: <code>xyzPosition</code> field.</li> <li>Bit 5: <code>NoisePower</code> field.</li> <li>Bit 6...10: These bits are reserved.</li> <li>Bit 11: <code>CICData</code> field.</li> <li>Bit 12: <code>SDData</code> field.</li> <li>Bit 13...15: These bits are reserved.</li> </ul> <p><b>Structure:</b> 16-bit Word read as a bit mask  <b>Range:</b> (0x0000...0xFFFF)</p>
<code>TimeStamp</code>	1	<p>8-Bit Counter of 200 Hz (Sample Interval)            200 Hz counter value wraps-around after 256 ticks. This indicates when an event has taken place and allows measuring the elapsed time between two events, as long as it is below approximately 1.25 seconds.</p> <p><b>Structure:</b> 8-bit Word read as decimal value.  <b>Range:</b> (0x00...0xFF)</p>



**TABLE 4-12: PAYLOAD ELEMENTS (CONTINUED)**

Element	Element size (bytes)	Description
SystemInfo	1	<p>Bit mask indicating if the respective sensor data is valid. In an application, the sensor data output should only be further processed if the respective bits are set to '1'.</p> <p>The following bits are used:</p> <ul style="list-style-type: none"> <li>Bit 0: PositionValid, if set indicates that the position in the xyzPosition field is valid.</li> <li>Bit 1: AirWheelValid, if set indicates that the AirWheel is active and the data in the AirWheelInfo field is valid.</li> <li>Bit 2: RawDataValid, if set indicates that the data of the CICData and SDData fields are valid; otherwise those fields must be ignored.</li> <li>Bit 3: NoisePowerValid, if set indicates that the NoisePower field is valid.</li> <li>Bit 4: EnvironmentalNoise, if set indicates that environmental noise has been detected.</li> <li>Bit 5: Clipping, if set indicates that the ADCs are clipping.<sup>(1)</sup></li> <li>Bit 6: This bit is reserved.</li> <li>Bit 7: DSPRunning, if set indicates that the system is currently running. If not set, the system is about to go to Sleep.</li> </ul> <p><b>Structure:</b> 8-bit Word read as a bit mask  <b>Range:</b> (0x00...0xFF)  <b>Note:</b> Position Data is disabled from the sensor data output and AirWheel is enabled: Position Valid will be set and sent with SystemInfo and a new message will be sent when AirWheel detection starts.</p>
DSPStatus	2	<p>This element consists of two bytes. The first byte contains information about Calibration events. The second byte indicates the Tx frequency currently used.</p> <ul style="list-style-type: none"> <li>Bit 0: This bit is reserved.</li> <li>Bit 1: CalibrationInfo: Forced Calibration (by Host)</li> <li>Bit 2: This bit is reserved.</li> <li>Bit 3: CalibrationInfo: Gesture triggered</li> <li>Bit 4: CalibrationInfo: Negative value</li> <li>Bit 5: CalibrationInfo: Idle Calibration</li> <li>Bit 6: CalibrationInfo: Invalid value Calibration</li> <li>Bit 7: CalibrationInfo: Calibration triggered by AFA</li> <li>Bits 8...15: Tx Frequency in kHz as decimal value (42...100)</li> </ul> <p><b>Structure:</b> 2 bytes; first byte is read as a bit mask while second as decimal  <b>Range:</b> (0x00...0xFF; 44...115)  <b>Note:</b> TX frequency is only reported when the frequency changes.</p>
<p><b>Note 1:</b> Clipping indication is not supported by MGC3140/MXG3141. Message is kept for compliance with MGC3x30.</p>		

# GestIC<sup>®</sup> Library Message Reference

TABLE 4-12: PAYLOAD ELEMENTS (CONTINUED)

Element	Element size (bytes)	Description
GestureInfo	4	<p>This field contains the 32-bit gesture information Word.</p> <p><b>Recognized Gestures:</b>  The recognized gestures are results of the HMM classification. Edge detection can be used to further classify where the gesture has been done (Edge Flicks). Furthermore, gesture attributes give information about the direction of the flick. The gesture information is given as a bit field and can be decoded as follows:</p> <ul style="list-style-type: none"> <li>Bits 0...7: Recognized gesture as decimal number <ul style="list-style-type: none"> <li>0: No gesture</li> <li>1: Garbage model</li> <li>2: Flick West to East</li> <li>3: Flick East to West</li> <li>4: Flick South to North</li> <li>5: Flick North to South</li> <li>6: Circle clockwise (only active if AirWheel disabled)</li> <li>7: Circle counterclockwise (only active if AirWheel disabled)</li> <li>8: Reserved</li> <li>9: Reserved</li> </ul> </li> <li>64: Hold</li> <li>65: Edge Flick West to East</li> <li>66: Edge Flick East to West</li> <li>67: Edge Flick South to North</li> <li>68: Edge Flick North to South</li> <li>69: Double Flick West to East</li> <li>70: Double Flick East to West</li> <li>71: Double Flick South to North</li> <li>72: Double Flick North to South</li> <li>73: Presence</li> <li>Bits 8...11: These bits must not be interpreted.</li> <li>Bits 12...15: Gesture Class read as a decimal number <ul style="list-style-type: none"> <li>0: Garbage model</li> <li>1: Flick gesture</li> <li>2: Circular gesture</li> </ul> </li> <li>Bit 16: Edge flick – is '1' if flick gesture is classified as edge flick</li> <li>Bits 17...26: These bits are reserved.</li> <li>Bit 27: HandPresence flag: Is '1' while the user's hand is within the sensing space.</li> <li>Bit 28: HandHold flag: Is '1' while the hand is not moving. Further dependencies can be adjusted inside Aurea Parameterization.</li> <li>Bit 29: HandInside flag: Is '1' while the user's hand is approximately above the sensor.</li> <li>Bit 30: This bit is reserved.</li> <li>Bit 31: Gesture recognition in progress. This bit is set when the Gesture Recognizer is active and Reset when the gesture is recognized and the Recognizer is Off.</li> </ul> <p><b>Structure:</b> 32-bit Word read as a bit mask  <b>Range:</b> (0x00000000...0xFFFFFFFF)</p>

**TABLE 4-12: PAYLOAD ELEMENTS (CONTINUED)**

Element	Element size (bytes)	Description
TouchInfo	4	<p>Contains touch information</p> <p>The following bits are used to indicate a touch event on the respective electrodes:</p> <ul style="list-style-type: none"> <li>Bit 0: Touch South electrode</li> <li>Bit 1: Touch West electrode</li> <li>Bit 2: Touch North electrode</li> <li>Bit 3: Touch East electrode</li> <li>Bit 4: Touch Center electrode</li> <li>Bit 5: Tap South electrode</li> <li>Bit 6: Tap West electrode</li> <li>Bit 7: Tap North electrode</li> <li>Bit 8: Tap East electrode</li> <li>Bit 9: Tap Center electrode</li> <li>Bit 10: Double Tap South electrode</li> <li>Bit 11: Double Tap West electrode</li> <li>Bit 12: Double Tap North electrode</li> <li>Bit 13: Double Tap East electrode</li> <li>Bit 14: Double Tap Center electrode</li> <li>Bit 15: This bit is reserved.</li> </ul> <p>Bits 16...23: Touch Counter: 8-bit counter; this counter determines the period between the time when the hand starts moving to touch until it is detected. This period is equal to [Touch Counter Value] x 5 (ms). The counter starts counting when the minimum approach speed required to detect a touch event is exceeded, until the touch is detected. After each touch detection, the counter is reset.</p> <p>Bits 24...31: These bits are reserved.</p> <p><b>Structure:</b> 32-bit Word read as a bit mask  <b>Range:</b> (0x00000000...0xFFFFFFFF)</p>
AirWheelInfo	2	<p>The first byte contains a counter which indicates how far the AirWheel rotation has progressed.</p> <ul style="list-style-type: none"> <li>Bits 0...4: Value represents the current angular position with a resolution of 32 counts for a full revolution.</li> <li>Bits 5...7: Counts of full rotations.</li> </ul> <p>Each time the angular position crosses '0', a full revolution is counted. If the user's hand is moving in clockwise direction, the counter is increased. For counterclockwise movements, the counter is decreased.</p> <p>AirWheelInfo is only valid if the AirWheelValid bit in the element SystemInfo is '1'.  The second byte is reserved.</p> <p><b>Structure:</b> Vector of two 8-bit Words read as a decimal value  <b>Range:</b> (0x0000...0x00FF)</p>

# GestIC<sup>®</sup> Library Message Reference

**TABLE 4-12: PAYLOAD ELEMENTS (CONTINUED)**

Element	Element size (bytes)	Description
xyzPosition	6	<p>This element contains x, y and z position data. Two bytes are used for each of the positions x, y and z.</p> <p>Bytes 1 and 2:x position Bytes 3 and 4:y position Bytes 5 and 6:z position</p> <p>The position information is only valid if the <code>PositionValid</code> bit in the element <code>SystemInfo</code> is '1'.</p> <p>The data give the position of the user's hand in the Cartesian coordinate system. Position data of [0, 0, 0] represent the origin of the coordinate system and data of [65535, 65535, 65535] are the maximum dimension of the sensing space. The origin is defined as the lower left corner of the sensitive space (South-West) at the surface of the system.</p> <p><b>Structure:</b> Vector of three 16-bit Words read as decimal value for each position x, y, z <b>Range:</b> (0x0000...0xFFFF) for each position x, y, z</p>
NoisePower	4	<p>Noise Power of the GestIC<sup>®</sup> system.</p> <p>NoisePower is only valid if the <code>NoisePowerValid</code> bit in the element <code>SystemInfo</code> is '1'.</p> <p><b>Structure:</b> 32-bit Word read as a float value <b>Range:</b> (0...3.402823e+38)</p>
CICData	20	<p>Uncalibrated Sensor Data (CIC Data)</p> <p><b>Structure:</b> Vector of five, 32-bit Words interpreted as float values in format. An offset of 32000 needs to be added to each channel. xxxx.xxxx.xxxx.xxxx.xxxx (South.West.North.East.Center or S1.S2.S3.S4.North) format <b>Range:</b> (-3.402823e+38...3.402823e+38) for each channel</p>
SDDData	20	<p>Signal Deviation (SD)</p> <p>SDDData are only valid if the <code>RawDataValid</code> bit in the element <code>SystemInfo</code> is '1'.</p> <p><b>Structure:</b> Vector of five, 32-bit Words interpreted as float values in xxxx.xxxx.xxxx.xxxx.xxxx (South.West.North.East.Center or S1.S2.S3.S4.North) format <b>Range:</b> (-3.402823e+38...3.402823e+38) for each channel</p>
Reserved	—	Reserved: Additional payload elements can be added in the future or for debug purposes.

**Note:** For the examples list of the `Sensor_Data_Output` command, refer to [Table A-3](#).

## Chapter 5. Messages for GestIC<sup>®</sup> Library Update

### 5.1 LIBRARY LOADER UPDATE PROCEDURE


The general library update process is shown in [Figure 5-1](#). Note that only libraries provided by Microchip Technology can be updated on the GestIC.

For the library update process, six different messages are used:

- FwUpdateStart
- FwUpdateStartPage
- FwUpdateToBuffer
- FwUpdateFlashBuffer
- FwUpdateVerify
- FwUpdateCompleted

**Note:** FwUpdateStart will erase all the library, so a partial update is not possible.

**FIGURE 5-1: LIBRARY UPDATE FLOWCHART**



# Messages for GestIC<sup>®</sup> Library Update

## 5.2 FwUpdateStart

This message starts the update session of the GestIC device.

Direction: Host to GestIC

**TABLE 5-1: MESSAGE OVERVIEW**

Header				Payload					
Msg. Size	Flags	Seq.	ID	Crc	SessionId	FlashKey	UpdateFunction	ErasePageStart	ErasePageEnd
1 Byte	1 Byte	1 Byte	1 Byte	4 Bytes	4 Bytes	8 Bytes	1 Byte	1 Byte	1 Byte
0x17	0x00	n/a	0x70	see description below					

**TABLE 5-2: PAYLOAD ELEMENTS**

Field	Size (in bytes)	Description
Crc	4	CRC is calculated across the following fields: SessionId, FlashKey, UpdateFunction, ErasePageStart and ErasePageEnd. The same CRC calculation algorithm is used in the bootloader and firmware, with Ethernet polynomial 0x04C11DB7.
SessionId	4	The SessionId is a random number generated by the Host, to be sent via FwUpdateStart message, and resent via FwUpdateCompleted message. SessionId must be '0' if 'UpdateFunction = Restart', and different from '0' in all other cases.
FlashKey	8	FlashKey is the following sequence of bytes used to unlock Flash memory operations: {0x55, 0x66, 0x99, 0xAA, 0xAA, 0x99, 0x66, 0x55}.
UpdateFunction	1	The UpdateFunction is used here in ProgramFlash. The valid values are:  <pre>ProgramFlash = 0,           // ProgramFlash VerifyOnly = 1,             // VerifyOnly WaitForHostCommand = 2,    // Wait for a host command Restart = 3                 // Do a restart with Reset</pre>
ErasePageStart	1	Must be '0'.
ErasePageEnd	1	Must be '0'.

**Note:** There are a total of 128 pages of program Flash memory. If 'UpdateFunction' is set to 'ProgramFlash', all of them will be erased to '0xFF' when message 'FwUpdateStart' is received by the device.

## 5.3 FwUpdateStartPage

This message stores the page number in an internal run-time variable, and initializes a 1K buffer with 0xFF.

Direction: Host to GestIC

**TABLE 5-3: MESSAGE OVERVIEW**

Header				Payload	
Msg. Size	Flags	Seq.	ID	Crc	PageNumber
1 Byte	1 Byte	1 Byte	1 Byte	4 Bytes	1 Byte
0x09	0x00	n/a	0x71	see description below	

**TABLE 5-4: PAYLOAD ELEMENTS**

Field	Size (bytes)	Description
Crc	4	CRC is calculated only for PageNumber
PageNumber	1	PageNumber indicates where to write in Flash memory with FwUpdateFlashBuffer message. The base memory address is given by PageNumber x 1024.

## 5.4 FwUpdateToBuffer

This message will copy the contents of Payload to the 1K buffer at Offset. The host must make sure that it does not write beyond the end of the 1K buffer. If the offset plus the length of data would go beyond the end of the buffer, a system status message with an error code will be sent by the bootloader, but the content will be written up until the end of the buffer. The length of Payload can be at maximum 128 bytes. It can be necessary to send more FwUpdateToBuffer messages to fill the 1K buffer with the required content.

Direction: Host to GestIC

**TABLE 5-5: MESSAGE OVERVIEW**

Header				Payload		
Msg. Size	Flags	Seq.	ID	Crc	Offset	Payload
1 Byte	1 Byte	1 Byte	1 Byte	4 Bytes	2 Bytes	1...128 Bytes
0x8A (max)	0x00	n/a	0x72	see description below		

**TABLE 5-6: PAYLOAD ELEMENTS**

Field	Size (bytes)	Description
Crc	4	CRC is calculated across Offset and Payload only.
Offset	2	Address Offset inside the buffer.
Payload	1...128	Data to store.

## 5.5 FwUpdateFlashBuffer

This message will flash the contents of the 1K buffer to Flash, but only if the `SessionId` is the same as was used with `FwUpdateStart`, the `PageNumber` is the same as used with the previous `FwUpdateStartPage` and less than the number of the last page, and the `BufferCrc` is correct for the current contents of the 1K buffer.

Direction: Host to GestIC

**TABLE 5-7: MESSAGE OVERVIEW**

Header				Payload				
Msg. Size	Flags	Seq.	ID	Crc	SessionId	BufferCrc	FlashKey	PageNumber
1 Byte	1 Byte	1 Byte	1 Byte	4 Bytes	4 Bytes	4 Bytes	8 Bytes	1 Byte
0x19	0x00	n/a	0x73	see <a href="#">Table 5-8</a>				

**TABLE 5-8: PAYLOAD ELEMENTS**

Field	Size (bytes)	Description
Crc	4	CRC is calculated across the following fields: <code>SessionId</code> , <code>BufferCrc</code> , <code>FlashKey</code> and <code>PageNumber</code>
SessionId	4	The <code>SessionId</code> is the same random number as used for the <code>FwUpdateStart</code> . <code>0x00000000</code> is an invalid <code>SessionId</code> and is used to force the device into a restart.
BufferCrc	4	<code>BufferCrc</code> is the CRC calculated for all the 1K buffer using Ethernet polynomial <code>0x04C11DB7</code> .
FlashKey	8	<code>FlashKey</code> is the following sequence of bytes used to unlock Flash memory operations: { <code>0x55</code> , <code>0x66</code> , <code>0x99</code> , <code>0xAA</code> , <code>0xAA</code> , <code>0x99</code> , <code>0x66</code> , <code>0x55</code> }.
PageNumber	1	<code>PageNumber</code> is the same value used in the previous <code>FwUpdateStartPage</code> message.



## 5.6 FwUpdateVerify

This message has the same payload as `FwUpdateFlashBuffer`, but will not flash the data.

Instead it will just compare it with the flash contents at that page and output a system status message with a `VerifyOk` or a `VerifyFailed` status. If any more pages need to be updated, a `FwUpdateStartPage` is expected and the whole previous procedure repeated for the rest of the pages.

Unlike `FwUpdateFlashBuffer`, this message can be used for the last Flash page as well.

Direction: Host to GestIC

**TABLE 5-9: MESSAGE OVERVIEW**

Header				Payload				
Msg. Size	Flags	Seq.	ID	Crc	SessionId	BufferCrc	FlashKey	PageNumber
1 Byte	1 Byte	1 Byte	1 Byte	4 Bytes	4 Bytes	4 Bytes	8 Bytes	1 Byte
0x19	0x00	n/a	0x74	see <a href="#">Table 5-10</a>				

**TABLE 5-10: PAYLOAD ELEMENTS**

Field	Size (bytes)	Description
Crc	4	CRC is calculated across the following fields: <code>SessionId</code> , <code>BufferCrc</code> , <code>FlashKey</code> and <code>PageNumber</code>
SessionId	4	The <code>SessionId</code> is the same random number as used for the <code>FwUpdateStart</code> . <code>0x00000000</code> is an invalid <code>SessionId</code> and is used to force the device into a restart.
BufferCrc	4	<code>BufferCrc</code> is the CRC calculated for all the 1K buffer using Ethernet polynomial <code>0x04C11DB7</code> .
FlashKey	8	<code>FlashKey</code> is the following sequence of bytes used to unlock Flash memory operations: { <code>0x55</code> , <code>0x66</code> , <code>0x99</code> , <code>0xAA</code> , <code>0xAA</code> , <code>0x99</code> , <code>0x66</code> , <code>0x55</code> }.
PageNumber	1	<code>PageNumber</code> is the same value used in the previous <code>FwUpdateStartPage</code> message.

## 5.7 FwUpdateCompleted

This message completes the update session of the GestIC.

Direction: Host to GestIC

**TABLE 5-11: MESSAGE OVERVIEW**

Header				Payload			
Msg. Size	Flags	Seq.	ID	Crc	sessionId	BufferCrc	FlashKey
1 Byte	1 Byte	1 Byte	1 Byte	4 Bytes	4 Bytes	4 Bytes	8 Bytes
0x18	n/a	n/a	0x77	see description below			

**TABLE 5-12: PAYLOAD ELEMENTS**

Field	Size (in bytes)	Description
Crc	4	CRC is calculated across the SessionId, BufferCRC, and FlashKey fields.
SessionId	4	The SessionId is the same random number as used for the FwUpdateStart.
BufferCrc	4	BufferCrc is the CRC calculated for all the 1K buffer using Ethernet polynomial 0x04C11DB7.
FlashKey	8	FlashKey is the following sequence of bytes used to unlock Flash memory operations: {0x55, 0x66, 0x99, 0xAA, 0xAA, 0x99, 0x66, 0x55}.

## Appendix A. I<sup>2</sup>C Command Examples

**TABLE A-1: REQUEST MESSAGE COMMAND EXAMPLES**

Requested Function			Request Message												Comment
			Header				Payload								
			Msg. Size	Flags	Seq.	ID	Msg. ID	Reserved			Parameter				
—	FW version (0x83)		0x0C	0x00	0x00	0x06	0x83	0x00	0x00	0x00	0x00	0x00	0x00	0x00	Fixed command.
Get Run-time Parameters	Electrode Mapping (0x0065, 0x0066, 0x0067, 0x0068, 0x0069)	Channelmapping_S	0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x65	0x00	0x00	0x00	Fixed command.
		Channelmapping_W	0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x66	0x00	0x00	0x00	
		Channelmapping_N	0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x67	0x00	0x00	0x00	
		Channelmapping_E	0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x68	0x00	0x00	0x00	
		Channelmapping_C	0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x69	0x00	0x00	0x00	
	Touch Detection (0x0097) and Approach Detection (0x0097)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x97	0x00	0x00	0x00	Fixed command.
	Approach Detection (0x0081)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x81	0x00	0x00	0x00	Fixed command.
	AirWheel (0x0090)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x90	0x00	0x00	0x00	Fixed command.
	Gesture Processing HMM (0x0085)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x85	0x00	0x00	0x00	Fixed command.
	Calibration Operation Mode (0x0080)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0x80	0x00	0x00	0x00	Fixed command.
	Data Output Enable Mask (0x00A0)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0xA0	0x00	0x00	0x00	Fixed command.
	Data Output Lock Mask (0x00A1)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0xA1	0x00	0x00	0x00	Fixed command.
	Data Output Request Mask (0x00A2)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0xA2	0x00	0x00	0x00	Fixed command.
	Gesture in Progress Flag Control (0x00A3)		0x0C	0x00	0x00	0x06	0xA2	0x00	0x00	0x00	0xA3	0x00	0x00	0x00	Fixed command.

**TABLE A-2: SET\_RUNTIME\_PARAMETER COMMAND EXAMPLES**

Requested Function			Set_Runtime_Parameter																Comment	
			Header				Payload													
			Msg. Size	Flags	Seq.	ID	Runtime Parameter ID		Reserved		Argument0				Argument1					
Common Category	Trigger (0x1000)	Force Calibration	0x10	0x00	0x00	0xA2	0x00	0x10	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	Fixed command.	
		Enter Deep Sleep 1	0x10	0x00	0x00	0xA2	0x00	0x10	0x00	0x00	0x00	0x02	0x00	0x00	0x00	0x00	0x00	0x00	Fixed command.	
		Enter Deep Sleep 2	0x10	0x00	0x00	0xA2	0x00	0x10	0x00	0x00	0x00	0x03	0x00	0x00	0x00	0x00	0x00	0x00	Fixed command.	
	MakePersistent (0xFF00)	Store RTPs for AFE	0x10	0x00	0x00	0xA2	0x00	0xFF	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	Fixed command.	
		Store RTPs for DSP	0x10	0x00	0x00	0xA2	0x00	0xFF	0x00	0x00	0x00	0x01	0x00	0x00	0x00	0x00	0x00	0x00	Fixed command.	
		Store RTPs for System	0x10	0x00	0x00	0xA2	0x00	0xFF	0x00	0x00	0x00	0x02	0x00	0x00	0x00	0x00	0x00	0x00	Fixed command.	
Analog Front-End Category	Electrode Mapping (0x0065, 0x0066, 0x0067, 0x0068, 0x0069)	Channelmapping_S	0x10	0x00	0x00	0xA2	0x65	0x00	0x00	0x00	0x03	0x00	0x00	0x00	0x00	0x00	0x00	Argument0 (8-bit) defines the respective Rx Channel for each electrode. This value can be '0' for Rx0, '1' for Rx1, '2' for Rx2, '3' for Rx3 or '4' for Rx4. These values are just examples.		
		Channelmapping_W	0x10	0x00	0x00	0xA2	0x66	0x00	0x00	0x00	0x01	0x00	0x00	0x00	0x00	0x00	0x00			
		Channelmapping_N	0x10	0x00	0x00	0xA2	0x67	0x00	0x00	0x00	0x02	0x00	0x00	0x00	0x00	0x00	0x00			
		Channelmapping_E	0x10	0x00	0x00	0xA2	0x68	0x00	0x00	0x00	0x04	0x00	0x00	0x00	0x00	0x00	0x00			
		Channelmapping_C	0x10	0x00	0x00	0xA2	0x69	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00			
Digital Signal Processing	TransFreqSelect (0x0082)	Five frequencies	0x10	0x00	0x00	0xA2	0x82	0x00	0x00	0x00	0x05	0x00	0x00	0x00	0x10	0x32	0x04	0x00	This is an example for five frequencies used in the following order (0x43210): ID 4, ID 3, ID2, ID 0	
		Two frequencies	0x10	0x00	0x00	0xA2	0x82	0x00	0x00	0x00	0x00	0x02	0x00	0x00	0x00	0x42	0x00	0x00	0x00	This is an example for two frequencies used in the following order (0x42): ID 4, ID 2
	Touch Detection (0x0097)	Enable	0x10	0x00	0x00	0xA2	0x97	0x00	0x00	0x00	0x00	0x08	0x00	0x00	0x00	0x08	0x00	0x00	0x00	Fixed command.
		Disable	0x10	0x00	0x00	0xA2	0x97	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x08	0x00	0x00	0x00	Fixed command.
	Approach Detection (0x0097)	Enable	0x10	0x00	0x00	0xA2	0x97	0x00	0x00	0x00	0x00	0x01	0x00	0x00	0x00	0x01	0x00	0x00	0x00	Fixed command.
		Disable	0x10	0x00	0x00	0xA2	0x97	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x01	0x00	0x00	0x00	Fixed command.

**TABLE A-2: SET\_RUNTIME\_PARAMETER COMMAND EXAMPLES (CONTINUED)**

Requested Function			Set_Runtime_Parameter																Comment
			Header				Payload												
			Msg. Size	Flags	Seq.	ID	Runtime Parameter ID	Reserved		Argument0				Argument1					
System Category	AirWheel (0x0090)	Enable	0x10	0x00	0x00	0xA2	0x90	0x00	0x00	0x00	0x20	0x00	0x00	0x00	0x20	0x00	0x00	0x00	Fixed command.
		Disable	0x10	0x00	0x00	0xA2	0x90	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x20	0x00	0x00	0x00	Fixed command.
	Gesture Processing HMM (0x0085)	Enable All Gestures	0x10	0x00	0x00	0xA2	0x85	0x00	0x00	0x00	0x7F	0x00	0x00	0x00	0x7F	0x00	0x00	0x00	The Argument0 (8-bit) defines which Gestures need to be configured. The Argument1 defines the mask for the Gestures which need to be configured. These values are just examples.
		Enable Only Flick Gestures	0x10	0x00	0x00	0xA2	0x85	0x00	0x00	0x00	0x1F	0x00	0x00	0x00	0x7F	0x00	0x00	0x00	
		Enable in Addition Circles	0x10	0x00	0x00	0xA2	0x85	0x00	0x00	0x00	0x60	0x00	0x00	0x00	0x60	0x00	0x00	0x00	
	Calibration Operation Mode (0x0080)	Enable	0x10	0x00	0x00	0xA2	0x80	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x3F	0x00	0x00	0x00	Fixed command.
		Disable	0x10	0x00	0x00	0xA2	0x80	0x00	0x00	0x00	0x3F	0x00	0x00	0x00	0x3F	0x00	0x00	0x00	Fixed command.
	Data Output Enable Mask (0x00A0)	Enable All Data	0x10	0x00	0x00	0xA2	0xA0	0x00	0x00	0x00	0x3F	0x18	0x00	0x00	0x3F	0x18	0x00	0x00	The Argument0 defines which Data need to be enabled or disabled. The Argument1 defines the mask for the Data which need to be configured. These values are just examples.
		Enable DSP, Gestures and Noise Power	0x10	0x00	0x00	0xA2	0xA0	0x00	0x00	0x00	0x23	0x00	0x00	0x00	0x3F	0x18	0x00	0x00	
		Enable Only Data: Noise (others not changed)	0x10	0x00	0x00	0xA2	0xA0	0x00	0x00	0x00	0x10	0x00	0x00	0x00	0x10	0x00	0x00	0x00	
		Disable Only Data: CIC (others not changed)	0x10	0x00	0x00	0xA2	0xA0	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x08	0x00	0x00	
	Data Output Lock Mask (0x00A1)	Lock All Data	0x10	0x00	0x00	0xA2	0xA1	0x00	0x00	0x00	0x3F	0x18	0x00	0x00	0x3F	0x18	0x00	0x00	The Argument0 defines which Data need to be locked or unlocked. The Argument1 defines the mask for the Data which need to be configured. These values are just examples.
		Lock DSP, Gestures and Noise Power	0x10	0x00	0x00	0xA2	0xA1	0x00	0x00	0x00	0x23	0x00	0x00	0x00	0x3F	0x18	0x00	0x00	
		Lock Only Data: Noise (others not changed)	0x10	0x00	0x00	0xA2	0xA1	0x00	0x00	0x00	0x10	0x00	0x00	0x00	0x10	0x00	0x00	0x00	
		UnLock Only Data: CIC (others not changed)	0x10	0x00	0x00	0xA2	0xA1	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x08	0x00	0x00	
	Data Output Request Mask (0x00A2)	Request All Data	0x10	0x00	0x00	0xA2	0xA2	0x00	0x00	0x00	0x3F	0x18	0x00	0x00	0x3F	0x18	0x00	0x00	The Argument0 defines which Data need to be requested. This is only valid for the next message. The Argument1 defines the mask for the Data which need to be configured. These values are just examples.
		Request DSP, Gestures and Noise Power	0x10	0x00	0x00	0xA2	0xA2	0x00	0x00	0x00	0x23	0x00	0x00	0x00	0x3F	0x18	0x00	0x00	
Request Only Data: Noise		0x10	0x00	0x00	0xA2	0xA2	0x00	0x00	0x00	0x10	0x00	0x00	0x00	0x10	0x00	0x00	0x00		
Gesture in Progress Flag Control (0x00A3)	Enable	0x10	0x00	0x00	0xA2	0xA3	0x00	0x00	0x00	0x01	0x00	0x00	0x00	0x01	0x00	0x00	0x00	Fixed command.	
	Disable	0x10	0x00	0x00	0xA2	0xA3	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x01	0x00	0x00	0x00	Fixed command.	

**TABLE A-3:    SENSOR\_DATA\_OUTPUT COMMAND EXAMPLES**

Requested Function	User Action	Sensor_Data_Output												Comment
		Header				Payload								
		Msg. Size	Flags	Seq.	ID	Data Output Config. Mask	Time Stamp	System Info	Parameter					
Data Output contains only DSPStatus field (configured using the Set_Runtime_Parameter command: 10 00 00 A2 A0 00 00 00 01 00 00 00 FF FF FF FF)	No action	0x0A	0x08	0x26	0x91	0x01	0x01	0x5D	0x80	0x10	0x73	—	—	Negative Calibration.
		0x0A	0x08	0x27	0x91	0x01	0x01	0x5E	0x80	0x00	0x73	—	—	Calibration finished.
		0x0A	0x08	0x28	0x91	0x01	0x01	0x5D	0x80	0x20	0x73	—	—	Idle Calibration.
		0x0A	0x08	0x29	0x91	0x01	0x01	0x5E	0x80	0x00	0x73	—	—	Calibration finished.
Data Output contains only Gesture Data field (configured using the Set_Runtime_Parameter command: 10 00 00 A2 A0 00 00 00 02 00 00 00 FF FF FF FF)	Flick East to west	0x0C	0x08	0x31	0x91	0x02	0x01	0x82	0x80	0x03	0x10	0x00	0x00	0x03: Flick East to West 0x10: Flick Gesture
		0x0C	0x08	0x32	0x91	0x02	0x01	0x83	0x80	0x00	0x00	0x00	0x00	
	Flick North to South	0x0C	0x08	0x33	0x91	0x02	0x01	0x13	0x80	0x05	0x10	0x04	0x00	0x05: Flick North to South 0x10: Flick Gesture
		0x0C	0x08	0x34	0x91	0x02	0x01	0x14	0x80	0x00	0x00	0x00	0x00	
	Flick South to North	0x0C	0x08	0x35	0x91	0x02	0x01	0x53	0x80	0x04	0x10	0x04	0x00	0x03: Flick South to North 0x10: Flick Gesture
		0x0C	0x08	0x36	0x91	0x02	0x01	0x54	0x80	0x00	0x00	0x00	0x00	
	Flick West to East	0x0C	0x08	0x37	0x91	0x02	0x01	0x5D	0x80	0x02	0x10	0x00	0x00	0x03: Flick West to East 0x10: Flick Gesture
		0x0C	0x08	0x38	0x91	0x02	0x01	0x5E	0x80	0x00	0x00	0x00	0x00	

**TABLE A-3: SENSOR\_DATA\_OUTPUT COMMAND EXAMPLES (CONTINUED)**

Requested Function	User Action	Sensor_Data_Output												Comment
		Header				Payload								
		Msg. Size	Flags	Seq.	ID	Data Output Config. Mask	Time Stamp	System Info	Parameter					
<p>Data Output contains only Gesture Data field (configured using the Set_Runtime_Parameter command: 10 00 00 A2 A0 00 00 00 02 00 00 00 FF FF FF FF)</p> <p>Gesture in Progress is activated using the Set_Runtime_Parameter command: 10 00 00 A2 A3 00 00 00 01 00 00 00 FF FF FF FF)</p>	Flick East to West	0x0C	0x08	0x3A	0x91	0x02	0x01	0x19	0x81	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x3B	0x91	0x02	0x01	0x45	0x81	0x03	0x10	0x00	0x00	Gesture recognized (Flick East to West)
		0x0C	0x08	0x3C	0x91	0x02	0x01	0x46	0x81	0x00	0x00	0x00	0x00	
	Just move hand	0x0C	0x08	0x3D	0x91	0x02	0x01	0x47	0x81	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x3E	0x91	0x02	0x01	0x6E	0x81	0x01	0x00	0x00	0x00	Garbage recognized
		0x0C	0x08	0x3F	0x91	0x02	0x01	0x6F	0x81	0x00	0x00	0x00	0x00	
	Flick East to West	0x0C	0x08	0x40	0x91	0x02	0x01	0x83	0x81	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x41	0x91	0x02	0x01	0xAC	0x80	0x03	0x10	0x04	0x00	Gesture recognized (Flick East to West)
		0x0C	0x08	0x42	0x91	0x02	0x01	0xAD	0x80	0x00	0x00	0x00	0x00	
	Flick North to South	0x0C	0x08	0x43	0x91	0x02	0x01	0x67	0x81	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x44	0x91	0x02	0x01	0x8A	0x80	0x05	0x10	0x04	0x00	Gesture recognized (Flick North to South)
		0x0C	0x08	0x45	0x91	0x02	0x01	0x8B	0x80	0x00	0x00	0x00	0x00	
	Flick South to North	0x0C	0x08	0x46	0x91	0x02	0x01	0x67	0x81	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x47	0x91	0x02	0x01	0x8E	0x80	0x04	0x10	0x04	0x00	Gesture recognized (Flick South to North)
		0x0C	0x08	0x48	0x91	0x02	0x01	0x8F	0x80	0x00	0x00	0x00	0x00	
	Flick West to East	0x0C	0x08	0x49	0x91	0x02	0x01	0x6E	0x81	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x4A	0x91	0x02	0x01	0x9A	0x80	0x02	0x10	0x02	0x00	Gesture recognized (Flick West to East)
		0x0C	0x08	0x4B	0x91	0x02	0x01	0x9B	0x80	0x00	0x00	0x00	0x00	
	Clockwise Circle	0x0C	0x08	0x4C	0x91	0x02	0x01	0x81	0x80	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x4D	0x91	0x02	0x01	0xD6	0x80	0x00	0x00	0x00	0x00	Circle Gesture not recognized because AirWheel is On
	Counter Clockwise Circle	0x0C	0x08	0x4E	0x91	0x02	0x01	0x05	0x80	0x00	0x00	0x00	0x80	Gesture Recognizer started
		0x0C	0x08	0x4F	0x91	0x02	0x01	0x56	0x80	0x00	0x00	0x00	0x00	Circle gesture not recognized because AirWheel is On

TABLE A-3: SENSOR\_DATA\_OUTPUT COMMAND EXAMPLES (CONTINUED)

Requested Function	User Action	Sensor_Data_Output												Comment
		Header				Payload								
		Msg. Size	Flags	Seq.	ID	Data Output Config. Mask		Time Stamp	System Info	Parameter				
Data Output contains only Touch Data field (configured using the Set_Runtime_Parameter command: 10 00 00 A2 A0 00 00 00 04 00 00 00 FF FF FF FF)	Touch Center Electrode	0x0C	0x08	0x45	0x91	0x04	0x01	0x51	0x81	0x10	0x00	0x09	0x00	Center Touch detected and the touch counter = 0x09
		0x0C	0x08	0x46	0x91	0x04	0x01	0x52	0x81	0x10	0x00	0x00	0x00	Touch Counter Reset
		0x0C	0x08	0x47	0x91	0x04	0x01	0x5D	0x81	0x00	0x02	0x00	0x00	Tap on Center electrode detected
		0x0C	0x08	0x48	0x91	0x04	0x01	0x5E	0x81	0x00	0x00	0x00	0x00	



## Appendix B. Glossary

**TABLE B-1: GLOSSARY**

Term	Definition
AFE	Analog front-end
Application Host	PC or embedded controller which controls the GestIC <sup>®</sup>
Aurea	GestIC <sup>®</sup> PC control software with graphical user interface
Colibri Suite	Embedded DSP suite within the GestIC <sup>®</sup> Library
Deep Sleep	GestIC <sup>®</sup> Power-Saving mode
E-field	Electrical field
Frame Electrodes	Rectangular set of four electrodes for E-field sensing
GestIC <sup>®</sup> Technology	Microchip's patented technology providing 3D free-space gesture recognition utilizing the principles of electrical near-field sensing
GestIC <sup>®</sup> Library	Includes the implementation of GestIC <sup>®</sup> features and is delivered as a binary file preprogrammed on the GestIC <sup>®</sup>
Gesture Recognition	Microchip's stochastic HMM classifier to automatically detect and classify hand movement patterns
Gesture Set	A set of provided hand movement patterns
Hand Brick	Copper-coated test block (40x40x70 mm)
Hillstar	MGC3130 Development Kit
HMM	Hidden Markov Model
Position Tracking	GestIC <sup>®</sup> technology feature
Sabrewing	MGC3x30 evaluation board
Self Wake-up	MGC3140 Power-Saving mode
Sensing Area	Area enclosed by the four-frame electrodes
Sensing Space	Space above sensing area
Signal Deviation	Term for the delta of the sensor signal on approach of the hand versus non-approach
Spacer Brick	Spacer between the sensor layer and hand brick (Styrofoam block 40x40xh mm) with h = 1/2/3/5/8/12 cm
SPU	Signal Processing Unit
Approach Detection	GestIC <sup>®</sup> technology feature: Power-Saving mode of the MGC3140 with approach detection (not supported by MXG3141)
Woodstar	MGC3030 Development Kit

## Worldwide Sales and Service

### AMERICAS

**Corporate Office**  
2355 West Chandler Blvd.  
Chandler, AZ 85224-6199  
Tel: 480-792-7200  
Fax: 480-792-7277  
Technical Support:  
<http://www.microchip.com/support>  
Web Address:  
[www.microchip.com](http://www.microchip.com)

**Atlanta**  
Duluth, GA  
Tel: 678-957-9614  
Fax: 678-957-1455

**Austin, TX**  
Tel: 512-257-3370

**Boston**  
Westborough, MA  
Tel: 774-760-0087  
Fax: 774-760-0088

**Chicago**  
Itasca, IL  
Tel: 630-285-0071  
Fax: 630-285-0075

**Dallas**  
Addison, TX  
Tel: 972-818-7423  
Fax: 972-818-2924

**Detroit**  
Novi, MI  
Tel: 248-848-4000

**Houston, TX**  
Tel: 281-894-5983

**Indianapolis**  
Noblesville, IN  
Tel: 317-773-8323  
Fax: 317-773-5453  
Tel: 317-536-2380

**Los Angeles**  
Mission Viejo, CA  
Tel: 949-462-9523  
Fax: 949-462-9608  
Tel: 951-273-7800

**Raleigh, NC**  
Tel: 919-844-7510

**New York, NY**  
Tel: 631-435-6000

**San Jose, CA**  
Tel: 408-735-9110  
Tel: 408-436-4270

**Canada - Toronto**  
Tel: 905-695-1980  
Fax: 905-695-2078

### ASIA/PACIFIC

**Australia - Sydney**  
Tel: 61-2-9868-6733

**China - Beijing**  
Tel: 86-10-8569-7000

**China - Chengdu**  
Tel: 86-28-8665-5511

**China - Chongqing**  
Tel: 86-23-8980-9588

**China - Dongguan**  
Tel: 86-769-8702-9880

**China - Guangzhou**  
Tel: 86-20-8755-8029

**China - Hangzhou**  
Tel: 86-571-8792-8115

**China - Hong Kong SAR**  
Tel: 852-2943-5100

**China - Nanjing**  
Tel: 86-25-8473-2460

**China - Qingdao**  
Tel: 86-532-8502-7355

**China - Shanghai**  
Tel: 86-21-3326-8000

**China - Shenyang**  
Tel: 86-24-2334-2829

**China - Shenzhen**  
Tel: 86-755-8864-2200

**China - Suzhou**  
Tel: 86-186-6233-1526

**China - Wuhan**  
Tel: 86-27-5980-5300

**China - Xian**  
Tel: 86-29-8833-7252

**China - Xiamen**  
Tel: 86-592-2388138

**China - Zhuhai**  
Tel: 86-756-3210040

### ASIA/PACIFIC

**India - Bangalore**  
Tel: 91-80-3090-4444

**India - New Delhi**  
Tel: 91-11-4160-8631

**India - Pune**  
Tel: 91-20-4121-0141

**Japan - Osaka**  
Tel: 81-6-6152-7160

**Japan - Tokyo**  
Tel: 81-3-6880-3770

**Korea - Daegu**  
Tel: 82-53-744-4301

**Korea - Seoul**  
Tel: 82-2-554-7200

**Malaysia - Kuala Lumpur**  
Tel: 60-3-7651-7906

**Malaysia - Penang**  
Tel: 60-4-227-8870

**Philippines - Manila**  
Tel: 63-2-634-9065

**Singapore**  
Tel: 65-6334-8870

**Taiwan - Hsin Chu**  
Tel: 886-3-577-8366

**Taiwan - Kaohsiung**  
Tel: 886-7-213-7830

**Taiwan - Taipei**  
Tel: 886-2-2508-8600

**Thailand - Bangkok**  
Tel: 66-2-694-1351

**Vietnam - Ho Chi Minh**  
Tel: 84-28-5448-2100

### EUROPE

**Austria - Wels**  
Tel: 43-7242-2244-39  
Fax: 43-7242-2244-393

**Denmark - Copenhagen**  
Tel: 45-4485-5910  
Fax: 45-4485-2829

**Finland - Espoo**  
Tel: 358-9-4520-820

**France - Paris**  
Tel: 33-1-69-53-63-20  
Fax: 33-1-69-30-90-79

**Germany - Garching**  
Tel: 49-8931-9700

**Germany - Haan**  
Tel: 49-2129-3766400

**Germany - Heilbronn**  
Tel: 49-7131-72400

**Germany - Karlsruhe**  
Tel: 49-721-625370

**Germany - Munich**  
Tel: 49-89-627-144-0  
Fax: 49-89-627-144-44

**Germany - Rosenheim**  
Tel: 49-8031-354-560

**Israel - Ra'anana**  
Tel: 972-9-744-7705

**Italy - Milan**  
Tel: 39-0331-742611  
Fax: 39-0331-466781

**Italy - Padova**  
Tel: 39-049-7625286

**Netherlands - Drunen**  
Tel: 31-416-690399  
Fax: 31-416-690340

**Norway - Trondheim**  
Tel: 47-7288-4388

**Poland - Warsaw**  
Tel: 48-22-3325737

**Romania - Bucharest**  
Tel: 40-21-407-87-50

**Spain - Madrid**  
Tel: 34-91-708-08-90  
Fax: 34-91-708-08-91

**Sweden - Gothenberg**  
Tel: 46-31-704-60-40

**Sweden - Stockholm**  
Tel: 46-8-5090-4654

**UK - Wokingham**  
Tel: 44-118-921-5800  
Fax: 44-118-921-5820